

Cloudera Edge Management 2.2.0

# Using Cloudera Edge Management

Date published: 2019-04-15

Date modified: 2024-07-23

# CLOUDERA

<https://docs.cloudera.com/>

# Legal Notice

© Cloudera Inc. 2024. All rights reserved.

The documentation is and contains Cloudera proprietary information protected by copyright and other intellectual property rights. No license under copyright or any other intellectual property right is granted herein.

Unless otherwise noted, scripts and sample code are licensed under the Apache License, Version 2.0.

Copyright information for Cloudera software may be found within the documentation accompanying each component in a particular release.

Cloudera software includes software from various open source or other third party projects, and may be released under the Apache Software License 2.0 (“ASLv2”), the Affero General Public License version 3 (AGPLv3), or other license terms. Other software included may be released under the terms of alternative open source licenses. Please review the license and notice files accompanying the software for additional licensing information.

Please visit the Cloudera software product page for more information on Cloudera software. For more information on Cloudera support services, please visit either the Support or Sales page. Feel free to contact us directly to discuss your specific needs.

Cloudera reserves the right to change any products at any time, and without notice. Cloudera assumes no responsibility nor liability arising from the use of products, except as expressly agreed to in writing by Cloudera.

Cloudera, Cloudera Altus, HUE, Impala, Cloudera Impala, and other Cloudera marks are registered or unregistered trademarks in the United States and other countries. All other trademarks are the property of their respective owners.

Disclaimer: EXCEPT AS EXPRESSLY PROVIDED IN A WRITTEN AGREEMENT WITH CLOUDERA, CLOUDERA DOES NOT MAKE NOR GIVE ANY REPRESENTATION, WARRANTY, NOR COVENANT OF ANY KIND, WHETHER EXPRESS OR IMPLIED, IN CONNECTION WITH CLOUDERA TECHNOLOGY OR RELATED SUPPORT PROVIDED IN CONNECTION THEREWITH. CLOUDERA DOES NOT WARRANT THAT CLOUDERA PRODUCTS NOR SOFTWARE WILL OPERATE UNINTERRUPTED NOR THAT IT WILL BE FREE FROM DEFECTS NOR ERRORS, THAT IT WILL PROTECT YOUR DATA FROM LOSS, CORRUPTION NOR UNAVAILABILITY, NOR THAT IT WILL MEET ALL OF CUSTOMER’S BUSINESS REQUIREMENTS. WITHOUT LIMITING THE FOREGOING, AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, CLOUDERA EXPRESSLY DISCLAIMS ANY AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, NON-INFRINGEMENT, TITLE, AND FITNESS FOR A PARTICULAR PURPOSE AND ANY REPRESENTATION, WARRANTY, OR COVENANT BASED ON COURSE OF DEALING OR USAGE IN TRADE.

# Contents

<b>Edge Flow Manager user interface.....</b>	<b>5</b>
Monitor.....	5
Edge Events.....	5
Design.....	6
Agent Manager.....	8
Resource Manager.....	9
Administration.....	9
<b>Deploying agents in CEM.....</b>	<b>10</b>
Using the Agent Deployer.....	10
Configuring the Agent Deployer for securing agents.....	19
<b>Managing agents in CEM.....</b>	<b>21</b>
Editing table layout in CEM.....	23
Viewing agent details in CEM.....	26
Debugging agent in CEM.....	29
Deleting agent class.....	31
<b>Expression language in CEM.....</b>	<b>32</b>
<b>Parameters in CEM.....</b>	<b>33</b>
Adding parameters in CEM.....	34
Referencing parameters in CEM.....	35
Using parameters in CEM.....	36
Setting agent parameter values.....	44
<b>Building a dataflow in CEM.....</b>	<b>45</b>
Adding components to the canvas in CEM.....	45
Configuring a processor in CEM.....	47
Configuring a remote process group in CEM.....	53
Adding services in CEM.....	54
Connecting components in CEM.....	56
Configuring a connection in CEM.....	57
Bending connections in CEM.....	58
Refreshing a dataflow in CEM.....	59
<b>Publishing a dataflow in CEM.....</b>	<b>59</b>
<b>Reverting a dataflow in CEM.....</b>	<b>60</b>
<b>Example dataflow in CEM.....</b>	<b>61</b>

<b>Managing flow versions.....</b>	<b>62</b>
Undo/redo draft changes.....	62
Switch between published flow versions.....	62
<b>Managing resources.....</b>	<b>63</b>
Resources tab.....	65
Resource management properties.....	67
<b>Monitoring deployments in CEM.....</b>	<b>67</b>
<b>Monitoring events in CEM.....</b>	<b>73</b>
<b>Monitoring metrics in CEM with Grafana.....</b>	<b>76</b>

## Edge Flow Manager user interface

The Edge Flow Manager (EFM) UI is designed to help you efficiently manage and monitor your dataflows and deployments. Learn how to use the UI to build, edit, publish, and revert dataflows, and monitor deployments and agent events.

To access the EFM UI, start the application, and navigate to the UI in a web browser by using the default address: `http://<hostname>:10090/efm/ui`.



**Note:** Replace <hostname> with the appropriate hostname for your environment.

Anyone with access to the CEM UI can view events and view or modify dataflows.

## Monitor

When you click Monitor in the left navigation, the **Dashboard** screen appears. This is the initial page of the Edge Flow Manager (EFM) UI that allows you to monitor C2 server and agent deployments.

When you navigate to the EFM UI for the first time, the Dashboard screen is displayed as shown in the following image:

Status	Class Name ↑	Number of Agents	Last Flow Updated	Updated Agents
Good Health	minifi-cpp-1.21.02.0-19	1	No flow has been published	>
Good Health	minifi-cpp-latest	3	No flow has been published	>
Good Health	minifi-java-1.2.2.2	1	No flow has been published	>
Good Health	minifi-java-latest	3	No flow has been published	>
Unknown Health	Unassigned	0	No flow has been published	>

For more detailed information on how to monitor deployments, see *Monitoring deployments in CEM*.

### Related Information

[Monitoring deployments in CEM](#)

## Edge Events

**Edge Events** allows you to monitor C2 server and agent events in Cloudera Edge Management (CEM).

When you navigate to the **Edge Events** in the Edge Flow Manager (EFM) UI, the screen is displayed as shown in the following image:

Date/Time ↓	Severity	Event Type	Message	Class Name	Source Type	Event Source ID
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	5f43eba2-72c2-4ee...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	ffb5baaa-02d3-455...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-1.2.2.2	Agent	a3217be3-bee8-41...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39e114ee-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39d18a6a-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39741e70-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-1.21.02...	Agent	48694392-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	5f43eba2-72c2-4ee...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	ffb5baaa-02d3-455...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-1.2.2.2	Agent	a3217be3-bee8-41...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39e114ee-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39d18a6a-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39741e70-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-1.21.02...	Agent	48694392-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...

For more detailed information on how to monitor server and agent events, see *Monitoring events in CEM*.

### Related Information

[Monitoring events in CEM](#)


## Design

Learn how to build and publish dataflows using the flow designer in Cloudera Edge Management (CEM).

### Open Flow

When you navigate to the flow designer in the Edge Flow Manager (EFM) UI, the **Open Flow** screen is displayed as shown in the following image. It shows the following information about the dataflows and classes in the system:

- Status
- Class
- Published Version
- Published On




You can sort data in each column in ascending or descending order by clicking the column name. For example, you can sort the dataflows based on which class they are associated with by clicking the Class column name.

You can also filter the data by class by using the Filter items search bar.

## Design


To build a dataflow, select the desired class from the table and click Open. Alternatively, you can double-click the desired class. The **Design** screen appears as shown in the following image:



The Design screen contains the following segments, each responsible for different functionalities of the application:

- **Components Toolbar:** Contains the components that you can drag onto the canvas to build your dataflow.
- **Services:** Shared services that can be used by processors and other services for configuration or task execution.
- **Parameters:** Allows you to parameterize the values of processor and service properties in the flow.

- **Actions:** A drop-down menu to open a different dataflow, publish a dataflow, or revert to the last published version of a dataflow.
- **Flow Status:** Displays information about the flow including when it was published, the last published version, and the status of the flow.



Modified ( ) indicates the flow has been modified since the flow has been published.



Current ( ) indicates the current published version of the flow.



**Note:** Once you open a dataflow, it is the default flow that displays in the **Design** screen. To build or edit another dataflow, click **ACTIONS** Open .

For more information on how to build a dataflow, see *Building a dataflow in CEM*. For more information on publishing a dataflow, see *Publishing a dataflow in CEM*.

### Related Information


[Building a dataflow in CEM](#)

[Publishing a dataflow in CEM](#)

## Agent Manager

The **Agent Manager** screen in Cloudera Edge Management (CEM) enables you to monitor the health of the agents, as well as view, filter, and initiate commands on specific agents.

When you navigate to the **Agent Manager** in the Edge Flow Manager (EFM) UI, the screen is displayed as shown in the following image:



Status	Class Name ↑	Flow Version	Agent ID	Last Seen
✓	minifi-cpp-1.21.02.0-19		48694392-ba7a-11ec-89e7-de74b8d...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39741e70-ba7a-11ec-b554-365471e...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39d18a6a-ba7a-11ec-a1c4-be3556c7...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39e114ee-ba7a-11ec-8ffc-2ed00cd6...	2022-04-13 05:56 CEST
✓	minifi-java-1.2.2.2		a3217be3-bee8-4187-b13e-4f16e50f...	2022-04-13 05:56 CEST
✓	minifi-java-latest		4a955dd1-a687-44a6-9371-102c50c...	2022-04-13 05:57 CEST
✓	minifi-java-latest		5f43eba2-72c2-4ee8-8d4d-a4dbaa44...	2022-04-13 05:57 CEST
✓	minifi-java-latest		ffb5baaa-02d3-4555-be61-3bcdbc0bf...	2022-04-13 05:57 CEST

For more information on how to manage agents, see *Managing agents in CEM*.

### Related Information


[Managing agents in CEM](#)



## Resource Manager

The Resource Manager screen enables you to upload new or manage existing assets and extensions in Cloudera Edge Management (CEM).

When you navigate to the Resource Manager in the Edge Flow Manager (EFM) UI, the screen is displayed as shown in the following image:



For more information on how to work with resources, see *Managing resources in CEM*.


### Related Information

[Managing resources in CEM](#)

## Administration

Authorization in Cloudera Edge Management (CEM) is linked to roles assigned to agent classes. These roles must be associated with authenticated users. The **Administration** screen enables you to manage the permissions of each user.

When you navigate to the **Administration** in the Edge Flow Manager (EFM) UI, the screen is displayed as shown in the following image:



The screenshot displays the Administration page in Cloudera Edge Management. The interface is split into two main sections: 'Users' and 'User Groups'. The 'Users' section contains a table with three entries: 'CN=monitoring-prometheus', 'Admin EFM', and 'Test User'. The 'User Groups' section contains a table with three entries: 'CEM', 'CEM-Admins', and 'CEM-JAVA'. A 'New User' button is visible in the top right of the Users section.

Users		
Name	Identity ↑	Administrator
CN=monitoring-prometheus	CN=monitoring-prometheus	
Admin EFM	efm_admin@cloudera.com	✓
Test User	test.test@example.com	

User Groups		
Name ↑	Members	Administrator
CEM	1	
CEM-Admins	2	✓
CEM-JAVA	2	

For more information on how to manage users and permissions, see *Access control policies*.

### Related Information

[Access control policies](#)


## Deploying agents in CEM

### Using the Agent Deployer

Learn how you can deploy a MiNiFi application using the Agent Deployer in the Edge Flow Manager (EFM).

## Procedure

1. Create a new agent class.
  - a) Click Monitor on the left menu bar to access the Dashboard page.
  - b) Click New Agent Class.



- c) Enter a name in the Agent Class Name text box and click Create.

The screenshot shows the 'New Agent Class' form. It has a title 'New Agent Class' and a label 'Agent Class Name'. The text box contains 'new-agent-class'. There are 'Cancel' and 'Create' buttons at the bottom right.

The new class is created and is added to the list of agent classes.



### Note:

If you already have an existing agent class, you may skip this step. Proceed with caution, when adding a new agent to an existing class. It is recommended to only add agents with the same version as the ones in the existing agent class to ensure the compatibility of agent manifests. If you are uncertain about the versions, start with a new agent class.

2. Create an agent repository.

Before deploying an agent, you need to create an agent repository under EFM to use the Deploy Agent functionality. The default binaries base directory is `${EFM_HOME_DIRECTORY}/agent-deployer/binaries`. You can customize the path by setting the `efm.agent-deployer.binariesRootPath` property in the `efm.properties` file.

Ensure your directory structure follows the convention `[{agentType}]/{osArch}/{agentVersion}`

Accepted values:

- agentType: java or cpp
- osArch: linux\*, windows\*, macos\* (This allows using different binaries for different OS versions.)
- agent version: Cloudera version of the agent (for example: 1.23.02)



### Note:

MacOS is only supported for testing purposes.

Each directory should contain only one file. While the file name can be any valid name, the extension must adhere to the following constraints:

- On Linux: Only the tar.gz file type should be used.
- On Windows:
  - For the Java agent type, the tar.gz format should be used.
  - For the CPP agent type, the MSI format should be used.


A few examples:

```
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/java/linux/1.23.02/minifi.tar.gz
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/java/linux/1.23.04/minifi.tar.gz
```

```
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/java/windows/1.23.02/minifi.  
tar.gz  
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/java/windows/1.23.04/minifi  
.tar.gz  
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/cpp/linux/1.23.03/minifi.t  
ar.gz  
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/cpp/linux/1.23.06/minifi.tar  
.gz  
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/cpp/windows32bit/1.23.03/m  
inifi.msi  
${EFM_HOME_DIRECTORY}/agent-deployer/binaries/cpp/windows64bit/1.23.06/min  
ifi.msi
```

**3. Generate Deploy Agent CLI command.**

- a) Click Monitor on the left menu bar to open the Dashboard with the list of agent classes.
- b) Click the created agent class to display the agent class details.
- c) Click Actions Deploy Agent Command .



If the agent repository has been created successfully in the previous step, the Agent Type, Agent Version, and OS drop-downs are pre-populated.

- d) Choose the desired options and click Generate.

### Deploy Agent CLI Command ✕

ⓘ Binaries are read from root [/var/s3fs/agent-deployer/binaries] with the expected folder structure of [{agentType}/{osArch}/{agentVersion}]

📁 CLASS NAME  
new-agent-class

Agent Type: java Agent Version and OS: v1.23.04 - Linux

Show Advanced Configurations

Cancel Generate

The generated command appears in the same window.

### Deploy Agent CLI Command ✕

i Binaries are read from root [/var/s3fs/agent-deployer/binaries] with the expected folder structure of [{agentType}]/{osArch}/{agentVersion}

CLASS NAME  
new-agent-class

Agent Type

java ▾

Agent Version and OS

v1.23.04 - Linux ▾

Show Advanced Configurations

i The generated command can only be used once, for a single agent deployment. Once executed, it can not be reused. Generate as many commands as agents to deploy.

#### Deploy Agent CLI Command

```

1 curl -L \
2   -d agentClass=new-agent-class \
3   -d agentIdentifier=007ac386-c406-4323-81e3-3cc85334cc74 \
4   -d agentType=java \
5   -d agentVersion=1.23.04 \
6   -d autoConfigureSecurity=false \
7   -d baseUrl=http%3A%2F%2Funsecure.cemcldr.link%2Fefm%2Fapi \
8   -d hbPeriod=5000 \
9   -d osArch=Linux \
10  -d serviceName=minifi \
11  -d serviceUser=minifi \
12  -d trustSelfSignedCertificates=false \
13  http://unsecure.cemcldr.link/efm/api/agent-deployer/script | bash -

```

Cancel
Generate

e) To install the agent, copy and paste the generated CLI command into the host where the agent will be installed.



**Note:**

Ensure the agent host has a network connection to EFM to successfully run the command.

#### 4. Set the advanced options for the Deploy Agent CLI command.

In specific scenarios, the default configuration may not meet your specific requirements. Use advanced configurations to customize parameters.

To make the advanced options visible, select the Show Advanced Configurations checkbox.

### Deploy Agent CLI Command

✕

Show Advanced Configurations

EFM Base URL

Agent ID

Heartbeat Period

Service User (applicable for Linux)

Service Name (applicable for Linux)

Autoconfigure Security

True  False

Self-Signed Certificates

Trust Self-Signed Certificates ?

CA Cert PEM File Location (Optional)

Dynamic Properties (Optional)

Property Name	Value	
		⊕ Add property

Cancel
Generate

#### EFM Base URL

The full URL of the EFM REST API base. The generated command uses this URL to access EFM from the remote host. If EFM is behind a load balancer or a proxy, you can override this URL.



**Note:** For a more sophisticated way to handle EFM behind a proxy, set the `efm.proxy.c2ProxyPath` property in the `efm.properties` file. This automatically sets the EFM Base URL to the correct value.

### Agent ID

The agent ID is automatically generated, but you can also set a custom value. If a custom value is set, make sure that each command generation has a unique identifier.

### Heartbeat Period

The agent sends heartbeats periodically using this value.

### Service User

- On Linux: A user is created with this name and the agent process runs under this user.
- On Windows: This is not applicable at the moment because the Java agent is not started as a service and the C++ agent is parameterized with the Service User.

### Autoconfigure Security

If security is enabled in EFM (for example any authentication method is turned on), the agent needs to connect to EFM in a secured manner. If Autoconfigure Security is enabled, EFM generates the necessary certificates for the agent, and the command downloads the certificates through a secured channel, and configures the agent automatically.

You can provide your own Certificate Authority (CA) for signing certificates. If a custom CA is not provided, EFM generates one during startup, which will be used for the certificates.



**Note:** To enable this feature, the following values must be set in the `efm.properties` file:

```
efm.agent-deployer.security.autoConfiguration=true
efm.agent-deployer.security.ca.privateKeyPassword=<strong_password>
```

For more information on Autoconfigure Security features, see *Configuring Agent Deployer for securing agents*.

### Self-Signed Certificates and CA Cert PEM File Location

If EFM is set up using a self-signed certificate (where EFM generated the CA and it was not provided externally), the request issued by the Agent Download command may be rejected since the issuing host will not trust EFM.

You have two options:

- Select the Trust Self-Signed Certificates checkbox to trust the self-signed certificate and proceed with the Agent Download command.
- Use the CA Cert PEM File Location to reference a CA Cert on the agent file system. This allows the agent to trust EFM by using the specified CA certificate.

### Dynamic properties:

You have the flexibility to override any arbitrary MiNiFi properties.

- For MiNiFi Java agents: The properties are located in the `bootstrap.conf` file.
- For MiNiFi C++ agents: The properties are located in the `minifi.properties` file.





```
-- Configuring MiNiFi...
-- Starting MiNiFi as a simple background process...
-- Waiting until MiNiFi is up...
-- OK
#Mon Jul 24 15:40:29 CEST 2023
port=64281
pid=87120
secret.key=451f4e40-15a5-4a58-8d18-63983fec927c

MiNiFi is now started as a background process.

You can stop it by issuing the following commands:

%> cd "minifi-1.23.04-b15"
%> bin/minifi.sh stop

To start again:
%> cd "minifi-1.23.04-b15"
%> bin/minifi.sh start

-- Installation has successfully completed.
   In addition of the existing (default) configuration values, the following have been applied:


---
c2.agent.identifier=061c6cf6-1922-41b7-8239-ad25a0f5be9a
c2.rest.path.heartbeat=/c2-protocol/heartbeat
c2.rest.path.acknowledge=/c2-protocol/acknowledge
c2.rest.url=http://unsecure.cemcldr.link/efm/api/c2-protocol/heartbeat
c2.rest.url.ack=http://unsecure.cemcldr.link/efm/api/c2-protocol/acknowledge
c2.agent.class=new-agent-class
c2.agent.heartbeat.period=5000
c2.enable=true
c2.rest.path.base=http://unsecure.cemcldr.link/efm/api
---
```

If you would like to modify this configuration, you need to perform these steps:

- 1) Stop MiNiFi
- 2) Edit the files located in "minifi-1.23.04-b15/conf"

### 3) Start MiNiFi

After successful installation, the agent sends heartbeats, appearing as an active agent in EFM.



#### Note:

- On Linux: both Java and C++ agents are started as a service using the Service User and Service Name parameters.
- On Windows:
  - Java agents run as a background process. The agents need to be manually restarted after an OS restart.
  - C++ agents are started as a service, but configuring the Service Name and Service User is not possible.

#### Related Information

[Configuring Agent Deployer for securing agents](#)

## Configuring the Agent Deployer for securing agents

Learn how you can establish a secure connection between the Edge Flow Manager (EFM) and the agents. EFM's agent deployer functionality provides a convenient approach for security configuration. By enabling auto-configuration, the deployment script automatically downloads a security bundle during agent setup, containing the agent's certificates along with its binary. This streamlined process ensures a robust and secure environment for seamless communication between EFM and agents.

There are two ways to sign the agent certificates:

- Using your own Intermediate CA key and certificate to sign the agent certificate

In this scenario, you need to place your own private key and certificate with the names `efm-cert.pem` and `efm-key.key` respectively under the folder specified in the `efm.agent-deployer.security.ca.location` property.

- Letting EFM generate a self-signed Root CA certificate

During EFM startup, the application checks if `efm-cert.pem` and `efm-key.key` are present in the configured folder. If they are missing, EFM generates them using the `efm.agent-deployer.security.ca.*` properties. In clustered mode, these certificates are synchronized between the EFM nodes as needed.

#### Minimal configuration

The default configuration is suitable for basic use cases. It enables security auto-configuration and generates a self-signed Root CA certificate, which is utilized for signing the agent certificates.

To enable this default configuration, ensure the following settings are in place:

```
efm.agent-deployer.security.autoConfiguration=true
efm.agent-deployer.security.ca.privateKeyPassword=password
```

Where:

- `efm.agent-deployer.security.autoConfiguration`  
Indicates the automatic generation of the Root CA and agent certificates.
- `efm.agent-deployer.security.ca.privateKeyPassword`  
Specifies the password for the private key of the root certificate.

### Advanced configuration

To enable this configuration, ensure the following settings are in place:

```
efm.agent-deployer.security.autoConfiguration=true
efm.agent-deployer.security.trustSelfSignedCertificates=true
efm.agent-deployer.security.accessTokenTtlMin=60
```

Where:

- `efm.agent-deployer.security.autoConfiguration`  
Enables the automatic generation of the root CA and agent certificates.
- `efm.agent-deployer.security.trustSelfSignedCertificates`  
Allows configuration to trust self-signed certificates by default or not. You can override this parameter anytime under Show Advanced Configurations in the UI.
- `efm.agent-deployer.security.accessTokenTtlMin`  
For security reasons, this parameter allows you to configure how long the generated command can be used after its generation.

### Root Certificate properties

These properties are used to generate the Root CA certificate. If you wish to use your own key and certificate, just set the `efm.agent-deployer.security.ca.privateKeyPassword` and `efm.agent-deployer.security.ca.location` properties and place the `efm-cert.pem` and `efm-key.key` files in this location.

```
efm.agent-deployer.security.ca.dn=CN=generated-efm-root-ca
efm.agent-deployer.security.ca.privateKeyAlgorithm=RSA
efm.agent-deployer.security.ca.privateKeyEncryptionAlgorithm=AES-256-CBC
efm.agent-deployer.security.ca.privateKeySize=4096
efm.agent-deployer.security.ca.privateKeyPassword=password
efm.agent-deployer.security.ca.certificateSigningAlgorithm=SHA256WITHRSA
efm.agent-deployer.security.ca.certificateValidityInDays=7305
efm.agent-deployer.security.ca.location=conf
```

Where:

- `efm.agent-deployer.security.ca.dn`  
Specifies the Distinguished Name (DN) of the self-signed root certificate (if you are not providing your own certificate).
- `efm.agent-deployer.security.ca.privateKeyAlgorithm`  
Sets the algorithm of the root certificate's private key (default: RSA).
- `efm.agent-deployer.security.ca.privateKeyEncryptionAlgorithm`  
Specifies the algorithm used for encrypting the root certificate's private key (default: AES-256-CBC).
- `efm.agent-deployer.security.ca.privateKeySize`  
Determines the number of bits for generated keys (default: 4096).
- `efm.agent-deployer.security.ca.privateKeyPassword`  
The password for the private key.

- `efm.agent-deployer.security.ca.certificateSigningAlgorithm`  
Sets the algorithm for root certificate generation (default: SHA256WITHRSA).
- `efm.agent-deployer.security.ca.certificateValidityInDays`  
Specifies the validity period of the root certificate in days. The default is 20 years, which can be adjusted based on the security requirements.
- `efm.agent-deployer.security.ca.location`  
The directory path where the `efm-key.key` and `efm-cert.pem` files are located.

### Agent Certificate properties

Agent keys and certificates are generated using these properties.

```
efm.agent-deployer.security.agent.privateKeyAlgorithm=RSA
efm.agent-deployer.security.agent.privateKeyEncryptionAlgorithm=AES-256-CBC
efm.agent-deployer.security.agent.privateKeySize=4096
efm.agent-deployer.security.agent.certificateSigningAlgorithm=SHA256WITHRSA
efm.agent-deployer.security.agent.certificateValidityInDays=7305
efm.agent-deployer.security.agent.keystoreType=JKS
efm.agent-deployer.security.agent.truststoreType=JKS
efm.agent-deployer.security.agent.location=conf
```

Where:

- `efm.agent-deployer.security.agent.privateKeyAlgorithm`  
Specifies the algorithm of the agent's private key (default: RSA).
- `efm.agent-deployer.security.agent.privateKeyEncryptionAlgorithm`  
Sets the algorithm for encrypting the agent's private key (default: AES-256-CBC).
- `efm.agent-deployer.security.agent.privateKeySize`  
Determines the number of bits for generated keys (default: 4096).
- `efm.agent-deployer.security.agent.certificateSigningAlgorithm`  
Sets the algorithm for signing agent certificates (default: SHA256WITHRSA).
- `efm.agent-deployer.security.agent.certificateValidityInDays`  
Specifies the validity period for agent certificates in days. The default is 20 years, which can be adjusted based on the security requirements.
- `efm.agent-deployer.security.agent.keystoreType`  
For Java agents, you can configure the keystore type (default: JKS, other options are BCFKS, PKCS12).
- `efm.agent-deployer.security.agent.truststoreType`  
For Java agents, you can configure the truststore type (default: JKS, other options are BCFKS, PKCS12).
- `efm.agent-deployer.security.agent.location`  
The folder in the agent's device where the keystore/truststore/key/cert is placed (default: conf).

## Managing agents in CEM

Learn about the Agent Manager and how to manage agents in Cloudera Edge Management (CEM).


The Agent Manager view provides you better understanding and more control over the agents in the system. The health of the agents can be easily monitored. Richer details about the agents can be retrieved. With the debug command option, live logs and configuration can be gathered without leaving EFM. With the property update functionality, the agent configuration can be changed through EFM.





**Note:** Not all agent versions are supporting remote command executions.

Learn about the options, available in the Agent Manager screen, that enable you to view, filter, and initiate commands on specific agents.

For better understanding and more control over the agents in the system, check out the video on the Cloudera Edge Management YouTube playlist:



To access the Agent Manager view, select the Agent Manager (  ) option from the menu. The Agent Manager screen appears, as shown in the following image:



Status	Class Name ↑	Flow Version	Agent ID	Last Seen
✓	minifi-cpp-1.21.02.0-19		48694392-ba7a-11ec-89e7-de74b8d...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39741e70-ba7a-11ec-b554-365471e...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39d18a6a-ba7a-11ec-a1c4-be3556c7...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39e114ee-ba7a-11ec-8ffc-2ed00cd6...	2022-04-13 05:56 CEST
✓	minifi-java-1.2.2.2		a3217be3-bee8-4187-b13e-4f16e50f...	2022-04-13 05:56 CEST
✓	minifi-java-latest		4a955dd1-a687-44a6-9371-102c50c...	2022-04-13 05:57 CEST
✓	minifi-java-latest		5f43eba2-72c2-4ee8-8d4d-a4dbaa44...	2022-04-13 05:57 CEST
✓	minifi-java-latest		ffb5baaa-02d3-4555-be61-3bcbdc0bf...	2022-04-13 05:57 CEST

## Editing Table Layout

CEM provides a dynamically editable table view to make the listing view as customizable as possible depending on your needs. For more information about how to customize the table view in Agent Manager screen, see *Edit table layout in CEM*.

## Sorting and filtering

You can sort data by most of the columns in ascending or descending order by clicking the column name. You can also filter the agents. To do this select the column name in the drop-down box at the top-right corner of the UI, enter the filter value, and press RETURN on the keyboard to apply the filter.

You can use multiple column names and filter values to filter your data. Here is an example of filtering by Status and Class Name:

Agent Manager

status: online × agentClass: minifi-cpp-latest × Filter by: Class Name

Status	Class Name ↑	Flow Version	Agent ID	Last Seen
✓	minifi-cpp-latest	1	49cb3c1e-bbdc-11ec-a08e-c6512...	2022-04-25 09:03 IST
✓	minifi-cpp-latest	1	49dfbcf2-bbdc-11ec-9650-f25f5c...	2022-04-25 09:03 IST
✓	minifi-cpp-latest	1	4a0edf46-bbdc-11ec-8d33-6a122...	2022-04-25 09:03 IST

Items per page: 25 1 - 3 of 3

### Items per page

You can set the displayed item count per page by using the Items per page dropdown at the bottom of the page near the pagination options. If there is more than one page available, you can use that navigation panel to jump to the first, previous, next, or straight to the last page.

### Viewing agent details

The agent details view is accessible through the View Agent Details icon in the extreme right of the given agent's row. For more information about viewing agent details, see *Agent details in CEM*.

For more information about Debug Command and Property Update Command, check out the video on the Cloudera Edge Management YouTube playlist:

## Editing table layout in CEM

Learn how to customize the agent listing view to suit your specific requirements efficiently.

With the table layout editor, you can change which attributes are displayed on the agent listing table and adjust the order of the columns as needed. To open the editor, click Edit Table Layout at the top-right corner of the screen, as shown in the following image:

Agent Manager

Monitor  
Edge Events  
Design  
Agent Manager

anonymous  
1.4.0.0-SNAPSHOT

CLLOUDERA Edge Management

Agent Manager

by: Status

Status	Class Name ↑	Flow Version	Agent ID	Last Seen
✓	minifi-cpp-1.21.02.0-19		48694392-ba7a-11ec-89e7-d674b8d...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39741e70-ba7a-11ec-b554-365471e...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39d18a6a-ba7a-11ec-a1c4-be3556c7...	2022-04-13 05:56 CEST
✓	minifi-cpp-latest		39e114ee-ba7a-11ec-8ffc-2ed00cd6...	2022-04-13 05:56 CEST
✓	minifi-java-1.2.2.2		a3217be3-bee8-4187-b13e-4f16e50f...	2022-04-13 05:56 CEST
✓	minifi-java-latest		4a955dd1-a687-44a6-9371-102c50c...	2022-04-13 05:57 CEST
✓	minifi-java-latest		5f43eba2-72c2-4ee8-8d4d-a4dbaa44...	2022-04-13 05:57 CEST
✓	minifi-java-latest		ffb5aaaa-02d3-4555-be61-3bcbdc0bf...	2022-04-13 05:57 CEST

Items per page: 25 1 - 8 of 8

The Edit Table Layout dialog appears:



## Edit Table Layout ✕

### Columns to Display

- All Columns
- Status
- Class Name
- Flow Version
- Agent ID
- Last Seen
- Last Flow Update
- Hostname
- IP
- Registered On
- Device Operating System
- Device Architecture
- Device Cores
- Device Memory
- Agent Type
- Agent Version

### Displayed Column Order

- Status
- Class Name
- Flow Version
- Agent ID
- Last Seen


You can select columns for display in the Columns to Display section on the left. You can change the order of display in the Displayed Column Order section by dragging and dropping items to the preferred order.

Additionally, you can bookmark or share the customized table layout by using the URL.

## Viewing agent details in CEM

Learn how to check individual agent details, monitor alerts, view configurations, check status, and track the history of triggered commands.

To access the specifics of an agent, click the View Agent Details icon (  ) in the right end of the agent's row. A dialog appears with the Metrics tab as the initial tab, as shown in the following image:



The screenshot shows the CEM Agent Manager interface. The main table lists several agents, all with a status of 'OK' (green checkmark) and class name 'minifi-java-latest'. The right-hand panel displays the details for the selected agent (ID: 01777de2-9a9c-4657-a435-57a9ef5e7084). The 'Metrics' tab is active, showing the following information:

AGENT ID	CLASS NAME
01777de2-9a9c-4657-a435-57a9ef5e7084	minifi-java-latest
FLOW VERSION	LAST SEEN
1	2022-04-23 12:15 IST
LAST FLOW UPDATE	HOSTNAME
2022-04-19 12:03 IST	unsecure-cem-agentjava-minifi-java-latest-84677c5fc5-zj4x6
IP ADDRESS	AGENT TYPE
10.80.142.70	minifi-java
AGENT VERSION	OPERATING SYSTEM
N/A	N/A
REGISTERED ON	DEVICE ARCHITECTURE
2022-04-14 15:51 IST	amd64
DEVICE MEMORY	MEMORY USAGE
495 MB	--
CPU UTILIZATION	DEVICE CORES
N/A	1
DEVICE ID	FLOW ID
eth0	d5f83cdb-9f29-48b6-9b77-62c0c835e23d

Below the information panel, there is a 'DASHBOARD' section with a link to 'View Grafana Dashboard' and a 'Repositories' section.

### Metrics tab


In the Information panel, you get a general overview of the agent's status, deployed flow version, and other useful device information. You can access the agent class details or the designer of the corresponding agent class by clicking the respective element.

The Repositories panel provides usage details of the repositories of the selected agent (where applicable).

The Connection Queues panel displays all connections used in a given agent accompanied by its metrics.

### Alerts tab


The Alerts tab display alerts from the past hours. For example, you can monitor if there was no heartbeat from the agent for a specific time, or when it became available again. To view all alerts, click the View all alerts link.




### Commands tab

In the Commands tab, you can check the last 20 commands sent to the agent along with their statuses. You can customize the number of displayed items using the `efm.agentManager.commands.displayLimit` property in the `efm.properties` file.


The details view may vary depending on the type of the command. For example, for Configuration Edit, you can check the affected property name, as shown in the following image:



If no update was required on the agent and the given agent had the new value already, you can see the message, as shown in the following image:



For debug requests, you are prompted with a Download Logs button to download the debug bundle retrieved from the agent, as shown in the following image:



### Configuration tab

In the Configuration tab, you can review the property configuration of an agent, provided the selected agent supports this functionality. Properties displayed can be filtered by both name and value.

The screenshot shows the Cloudera Edge Management interface. On the left, the 'Agent Manager' section is active. The main area displays a table of agents:

Status	Class Name	File
✓	minifi-cpp-1.21.02.0-19	
✓	minifi-cpp-latest	1
✓	minifi-cpp-latest	1
✓	minifi-cpp-latest	1
✓	minifi-java-1.2.2.2	1
✓	minifi-java-latest	1
✓	minifi-java-latest	1
✓	minifi-java-latest	1

The right panel shows the 'Agent Property Configuration' for agent ID 49cb3c1e-bbdc-11ec-a08e-c6512ecb9d64. It includes a search bar and a list of properties:

- NIFI.C2.MQTT.CONNECTOR.SERVICE: No value has been set for this property.
- NIFI.FLOW.CONFIGURATION.FILE.EXIT.ONFAILURE: No value has been set for this property.
- NIFI.C2.MQTT.UPDATE.TOPIC: No value has been set for this property.
- NIFI.FLOWFILE.REPOSITORY.MAX.STORAGE.SIZE: No value has been set for this property.
- NIFI.REMOTE.INPUT.SECURE: false
- NIFI.FLOW.CONFIGURATION.BACKUP.ON.UPDATE: No value has been set for this property.
- NIFI.LOG.APPENDER.SYSLOG: No value has been set for this property.
- NIFI.LOG.SPDLLOG.PATTERN: No value has been set for this property.
- NIFI.PROVENANCE.REPOSITORY.MAX.STORAGE.TIME: No value has been set for this property.
- NIFI.BORED.YIELD.DURATION: 10 millis



**Note:** This feature is only supported with the following agent versions:

- minifi-cpp 1.22.04 or higher
- minifi-java 1.23.02 or higher

CEM also supports editing properties at agent class level. For more information, see *Monitoring deployments in CEM*.

### Debug Agent button

The debug command functionality allows you to collect debug information from agents using the C2 protocol. For more information, see *Debugging agent in CEM*.

### Related Information


[Debugging agent in CEM](#)

[Monitoring deployments in CEM](#)


## Debugging agent in CEM

Learn how to use the debug command functionality which allows you to collect debug information from agents utilizing the C2 protocol.

Execute the debug command to initiate the operation to the agent by using the Debug Agent button, as shown in the following image:



This operation command initiates the debug request within the next heartbeat to the agent, and the view shifts to the Commands tab. The following image shows that the debug request is in progress:



When the agent receives it in the next heartbeat, it starts to upload the files to the EFM server.

When the files are available in the EFM server, a download button appears in the command details.

You can control the maximum uploadable file size by changing the `efm.data.transfer.maxFileSize` parameter. The default value of the parameter is 16 MB which is the maximum value supported by the current storage implementation.

**Note:**

- The debug operation is supported only for CPP agents from a minimum version of 1.22.01 and for Java agents from a minimum version of 1.22.10.
- The agent debug option is available only for the operators in a secure environment. For more information, see *Policies for agent class roles*.

**Related Information**

[Policies for agent class roles](#)

## Deleting agent class

Learn how you can delete agent classes on the EFM UI.

**About this task**

You can delete an agent class in EFM if authentication is not enabled in your environment or if you have admin rights in an authenticated environment.

When you delete an agent class, it also removes the flow assigned to that class, but events associated with the deleted class will remain available in the Edge Events view. EFM does not provide any rollback option. You have to export the flow before deleting it, if you want to restore it in the future.

**Procedure**


1. Click Monitor in the left navigation panel to open the Dashboard.
2. Locate the agent class you want to delete and open Agent Class Details.
3. Click Actions Delete Agent Class .



**Note:** You can only delete an agent class if no online agent is assigned to it.

The screenshot shows the Cloudera Edge Management (CEM) interface. On the left is a navigation panel with 'Monitor' selected. The main area is the 'Dashboard' for 'Class A', which shows a table with columns 'Status' and 'Class Name'. The table contains two rows: 'Class A' with status 'Unknown Health' and 'Unassigned' with status 'Unknown Health'. Below the table, the 'Flow Definition' section displays a message: 'No Manifest available! Wait for Agents to connect or Import a New Flow'. On the right side, an 'Actions' dropdown menu is open, listing several options: 'Deploy Agent CLI Command', 'Manage Agents', 'Import Flow', 'Export Flow', and 'Delete Agent Class', which is highlighted.

4. Confirm that you want to delete the agent class.






Once confirmed, the agent class is deleted from the system.

## Expression language in CEM

The NiFi Expression Language provides the ability to reference the attributes of flow files, compare them to other values, and manipulate their values.

As you extract attributes from content of the flow files and add user-defined attributes, they do not help much as an operator unless you have some mechanism by which you can use them. The NiFi Expression Language allows you to access and manipulate FlowFile attribute values as you configure your flows. Not all processor properties allow the Expression Language to be used, but many do. In order to determine whether or not a processor or service property supports the Expression Language, click in the property value field. The eligibility indicators show if Expression

Language is supported (  ) or unsupported (  ). Additionally, you can hover over the help icon (  ) next to the property name. The help icon provides a tooltip that displays the Expression Language scope.

To configure an eligible property to utilize Expression Language, use the \$ symbol as the start, with the expression enclosed in curly braces:

```
${Expression}
```

If you start your new entry with the start delimiter \${, selecting the keystroke control+space shows a list of available functions. Help text describing this process appears when you hover over the Expression Language eligibility indicator.




An expression can be as simple as an attribute name. For example, to reference the uuid attribute, you can simply use the value `${uuid}`. If the attribute name begins with any character other than a letter, or if it contains a character other than a number, a letter, a period (`.`), or an underscore (`_`), you need to quote the attribute name. For example, `${My Attribute Name}` is not valid, but `${'My Attribute Name'}` refers to the My Attribute Name attribute.

## Parameters in CEM

Parameters provide the ability to parameterize the values of processors and service properties in the flow including sensitive properties. You can create and configure parameters in the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

To determine whether a parameter can be used for a property, click in the property value field. The eligibility

indicators show if parameters are supported ( ✓ ) or unsupported ( ✗ ).



**Note:** Properties that reference services can not use parameters.


## Adding parameters in CEM

Learn how to add parameters using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure

1. To add a parameter, click the Parameters button at the bottom-left corner of the canvas, or simply right-click on the canvas and select Parameters.

The Parameters window appears as shown in the following image:



- Click the ADD PARAMETER button.

The Add Parameter window dialog appears as shown in the following image:

The screenshot shows the 'Add Parameter' dialog box. It has a title bar with a close button (X). The dialog contains the following fields and controls:

- Name\***: A text input field with a blue border, containing the placeholder text 'Name'.
- Value**: A text input field with a gray border, containing the placeholder text 'VALUE'.
- Set empty string**: A checkbox that is currently unchecked.
- Sensitive Value**: Two radio buttons, 'Yes' and 'No'. The 'No' radio button is selected.
- Description**: A text input field with a gray border, containing the placeholder text 'Description'. A character count '0/1000' is visible in the top right corner of the field.
- Buttons**: 'Cancel' and 'Add' buttons are located at the bottom right of the dialog.

- Configure the following properties:

Property	Description
Name	Enter a name that is used to denote a parameter. Only alpha-numeric characters (a-z, A-Z, 0-9), hyphens ( - ), underscores ( _ ), periods ( . ), and spaces are allowed.
Value	Enter a value that is used when the parameter is referenced. Parameter values do not support Expression Language or embedded parameter references.
Set empty string	Select the checkbox to set parameter value to an empty string.
Sensitive Value	Set whether the parameter value should be considered sensitive. If so, the value of the parameter is not shown in the UI once applied. Once you create a parameter, its sensitivity flag cannot be changed.
Description	Enter a description that explains what the parameter is for. This field is optional.

- Click Add button to add the parameter.
- Click Apply button to save the changes.

## Referencing parameters in CEM

Learn how to reference parameters using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

To configure an eligible property to reference a parameter, use the # symbol as the start, with the name of the parameter enclosed in curly braces:

```
# {Parameter . Name }
```

This can be escaped using an additional # character at the beginning. To illustrate this, assume that the parameter abc has a value of xxx and parameter def has a value of yyy. Then, the following user-defined property values will evaluate to these effective values:

User-Entered Literal Property Value	Effective Property Value	Explanation
<code>{abc}</code>	xxx	Simple substitution
<code>{abc}/data</code>	xxx/data	Simple substitution with additional literal data
<code>{abc}/{def}</code>	xxx/yyy	Multiple substitution with additional literal data
<code>{abc}</code>	<code>{abc}</code>	No { } for parameter replacement
<code>#abc</code>	<code>#abc</code>	No { } for parameter replacement
<code>#{abc}</code>	<code>{abc}</code>	Escaped # for literal interpretation
<code>###{abc}</code>	<code>xxx</code>	Escaped # for literal interpretation, followed by simple substitution
<code>####{abc}</code>	<code>#{abc}</code>	Escaped # for literal interpretation, twice
<code>#####{abc}</code>	<code>###xxx</code>	Escaped # for literal interpretation, twice, followed by simple substitution
<code>{abc/data}</code>	Exception thrown on property set operation	/ not a valid parameter name character

When referencing a parameter from within expression language, the parameter reference is evaluated first. As an example, to replace xxx with zzz for the abc parameter:

```
{ {abc}:replace('xxx', 'zzz') }
```

## Using parameters in CEM

Learn how to use parameters in Cloudera Edge Management (CEM).

Parameters can be easily referenced or created as you configure the components in your flow.

### Referencing existing parameters

Existing parameters can be referenced for a processor or service property value.

1. To reference an existing parameter, select the property value field and clear the default value if one exists.

2. Enter the start delimiter #{\.



FetchFile (Processor)

## Configuration

Property	Value	
File to Fetch		↑
Completion Strategy		↑
Move Destination Directory		↑
Move Conflict Strategy		↑
Log level when file not found		↑
Log level when permission denied	ERROR	↑

EL ✓ PARAM ✓

```
1 #{\.
```

Set empty string

Cancel Ok

## About

PROCESSOR ID  
c0745798-2968-4b02-a4fe-52e27999585a

PROCESSOR TYPE  
FetchFile 1.3.1


BUNDLE  
org.apache.nifi.minifi - minifi-standard-nar

## Comments

Describe the changes made in this update

Apply

- If you know the parameter you want to reference, enter its name. Alternatively, select the keystroke control+space to show the list of available parameters:



- 4. Complete the entry with a closing curly brace } and select Ok.

»

FetchFile (Processor)  
**Configuration**

Property	Value
File to Fetch	<div style="border: 1px solid #ccc; padding: 5px;"><span style="float: right;">EL ✓ PARAM ✓</span><pre>1 #file1-paramter</pre><input type="checkbox"/> Set empty string <span style="float: right;">Cancel Ok</span></div>
Completion Strategy	
Move Destination Directory	
Move Conflict Strategy	
Log level when file not found	
Log level when permission denied	<span>?</span> ERROR

**About**

PROCESSOR ID  
c0745798-2968-4b02-a4fe-52e27999585a

PROCESSOR TYPE  
FetchFile 1.3.1

BUNDLE  
org.apache.nifi.minifi - minifi-standard-nar

**Comments**

Describe the changes made in this update

Apply

5. Click Apply to save the changes.

Help text describing this process appears when you hover over the Expression Language and Parameters eligibility indicators.

»

FetchFile (Processor)

## Configuration

Property	EL	PARAM	
File to Fetch	✓	✓	↑
Completion Strategy			↑
Move Destination Directory			↑
Move Conflict Strategy			↑
Log level when file not found			↑
Log level when permission denied	?	ERROR	↑

✓ **Expression Language (EL) supported**  
After beginning with the start delimiter `$(` use `Ctrl+Space` to see a list of available functions.

✓ **Parameters (PARAM) supported**  
After beginning with the start delimiter `#(` use `Ctrl+Space` to see a list of available parameters.

```
1 #(file1-paramter)
```

Set empty string

## About

PROCESSOR ID  
c0745798-2968-4b02-a4fe-52e27999585a

PROCESSOR TYPE  
FetchFile 1.3.1

BUNDLE  
org.apache.nifi.minifi - minifi-standard-nar

## Comments

Describe the changes made in this update


Apply


## Converting property values to parameters

Parameters can be created during process or service configuration. Instead of entering a property value, you can convert the property value to a parameter.




1.

To create a parameter for a property value, select the Convert to parameter icon (  ) in the row of that property.



The Create Parameter dialog appears as shown in the following image:



2. Configure the parameter properties.

- Click Add to add the parameter. The property references the new parameter with the proper syntax applied automatically.

Design / Agent Class

minifi-java-latest

GetFile

Configuration

Property	Value
Input Directory	#(Input Directory)
File Filter	["\."*
Path Filter	No value set
Batch Size	10
Keep Source File	false
Recurse Subdirectories	true
Polling Interval	0 sec
Ignore Hidden Files	true
Minimum File Age	0 sec
Maximum File Age	No value set
Minimum File Size	0 B
Maximum File Size	No value set

Apply

- Click Apply to save the changes.

### Converting selectable property values to parameters

Property values that are selectable can also reference parameters.

- Select the property value drop-down. The option Reference parameter... is available for eligible properties.

Design / Agent Class

minifi-java-latest

FetchFile

Configuration

Property	Value
File to Fetch	\$(absolute.path)/\$(filename)
Completion Strategy	None
Move Destination Directory	
Move Conflict Strategy	
Log level when file not found	Delete File
Log level when permission denied	Reference parameter...

About

PROCESSOR ID  
c170e13d-89b9-49a0-bab6-fb900ecb96ab

PROCESSOR TYPE  
FetchFile 1.3.1

BUNDLE  
org.apache.nifi.minifi - minifi-standard-nar

Comments

Describe the changes made in this update

Apply

2. Select Reference parameter... option. A list of parameters to choose appears.

The screenshot shows the Cloudera Edge Management (CEM) interface. On the left is a navigation sidebar with options: Monitor, Edge Events, Design (selected), and Agent Manager. The main workspace is titled 'Design / Agent Class' and shows a 'minifi-java-latest' processor. A 'FetchFile' component is highlighted with a blue circle. On the right, the 'Configuration' panel for 'FetchFile (Processor)' is visible. It includes a table of properties and values, an 'About' section with processor details, and a 'Comments' section. The 'Completion Strategy' dropdown menu is open, showing a list of parameters to choose from: 'Reference parameter...', 'strategy-1', 'strategy-2', and 'strategy-3'. An 'Apply' button is located at the bottom right of the configuration panel.

3. Select a parameter and click OK.
4. Click Apply to save the changes.

### Referenced parameters

When parameters have been referenced in the flow, the Parameters window lists all the components that use them in the Referenced By section.

The screenshot shows the Cloudera Edge Management (CEM) interface with the 'Parameters' window open. The main workspace shows a 'minifi-java-latest' processor with three components: 'FetchFile', 'GenerateFlowFile', and 'FetchSFTP'. The 'Parameters' window on the right has an 'ADD PARAMETER' button and a table of parameters. The 'Referenced By' section is expanded, showing the processors and services that reference the selected parameters.

Name	Value	Description
file-size	10B	
password-1	*****	
strategy-1	strategy-1	
strategy-2	strategy-2	
strategy-3	strategy-3	

**Referenced By**

Processors

- FetchFile
- GenerateFlowFile
- FetchSFTP

Services


- StandardRestrictedSSLContextService

Select a specific parameter to see the processors and services that reference just that parameter.

## Using parameters with sensitive properties

Non-sensitive properties should only reference non-sensitive parameters. Sensitive properties should only reference sensitive parameters. This is important when publishing versioned flows. The value of the sensitive parameter itself is not sent to the flow registry, but only the fact that the property references the sensitive parameter.

If a non-sensitive property references a sensitive parameter, or vice-versa, the UI marks the component as invalid:



## Setting agent parameter values

Learn about parameter context and how to set agent parameter values in Cloudera Edge Management (CEM).

Any collection of replacement key-value pairs is known as a parameter context. Parameters never exist on their own. They only exist in a parameter context. Edge Flow Manager (EFM) allows setting parameter contexts at the following levels:

Levels	Description
Flow	The flow level parameter context acts as a default for the entire flow. If there are no agent class or agent level parameter context mappings set, the flow parameter context is used. You can manage the values for this level in the UI in the <b>Flow Designer</b> by clicking Parameters in the lower left corner. Every time a flow is published, a copy of the current parameter context from the <b>Flow Designer</b> gets copied to the flow level parameter context for the published flow. Therefore, changing the values for parameters in the <b>Flow Designer</b> does not update previously published flows.
Agent Class	An agent class level parameter context, if present, overwrites the flow level context. This is to support multiple versions of a flow definition to an agent class, but allowing agent class configuration values that override whatever is set in the <b>Flow Designer</b> UI as default values. Agent class level parameter contexts are set using the EFM REST API, and can be set once to impact all future flows published to that agent class.
Agent	An agent level parameter context, if present, overwrites the agent class and flow level contexts. This is to support deploying a flow to multiple agents in an agent class but allowing per-agent configuration values. Agent level parameter contexts are set using the EFM REST API, and can be set once to affect all future flows deployed to that agent.

### Resolving parameter contexts

When an agent requests a flow from EFM, EFM substitutes parameter values just-in-time for placeholders by resolving parameter values in this hierarchy of contexts. In order to accomplish this, the flow URI that EFM sends to agents as part of a flow update operation looks like the following:

```
GET /efm/api/flows/{flowId}?aid={agentId}
```

When a flow is fetched, the agent, agent class, and flow level parameter contexts are retrieved and applied to the flow in the hierarchy listed above.

### REST API endpoints for parameters

For information about creating parameter contexts and mapping them to flows, agent classes, and agents, see the following:

- Parameters section in *Cloudera Edge Flow Manager REST API*.
- Parameter Mappings section in *Cloudera Edge Flow Manager REST API*.

For tutorials of specific use cases that leverage this feature, including examples interacting with the REST API using curl, see *Using Agent Parameters*.

### Related Information

[REST API Reference](#)

[Using agent parameters](#)

## Building a dataflow in CEM

You can build an automated dataflow using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM). Simply drag components from the toolbar to the canvas, configure the components to meet specific needs, and connect the components together.


For additional information about flow creation and related concepts, check out the video on the Cloudera Edge Management YouTube playlist:

## Adding components to the canvas in CEM

Learn how to add each of the components available in the Components Toolbar in the Edge Flow Manager (EFM) UI. You can add processors, remote process groups, and funnels.

### Processor

The processor is the most commonly used component, as it is responsible for data ingress, egress, routing, and manipulating. There are many different types of processors. When you drag a processor onto the canvas, the Add Processor dialog appears, as shown in the following image, which allows you to choose which type of processor to use:




You can filter the list based on the processor type by using the Filter items field at top-right corner of the Add Processor dialog. After selecting a processor, you can click the Add button to add the selected processor to the canvas at the location that it was dropped. Alternatively, you can double-click on a processor type.



**Note:** For any component added to the canvas, it is possible to select it with the mouse and move it anywhere on the canvas. Also, it is possible to move all items at once by clicking and dragging the mouse on the canvas.


After you drag a processor onto the canvas, you can configure properties of the processor, parameterize processor property values, or delete the processor. To configure properties, double-click on the processor, or right-click on the processor and select Configure from the context menu. To delete a processor, right-click on the processor and select Delete from the context menu, or highlight the processor and select DELETE on your keyboard. The following image shows the Configure and Delete options in the context menu:



## Remote process group

A Remote Process Group (RPG) references a remote instance of NiFi. When you drag an RPG onto the canvas, rather than being prompted for a name, you are prompted for the URL of the remote NiFi instance. If the remote NiFi is clustered, you need to provide at least one URL of any NiFi instance in that cluster. When data is transferred from an RPG running in MiNiFi, the RPG first connects to the remote instance whose URL is configured to determine which nodes are in the cluster and how busy each node is. This information is then used to load balance the data that is pushed to each node. The remote instances are then interrogated periodically to determine information about any nodes that are dropped from or added to the cluster and to recalculate the load balancing based on the load of each node. If the cluster node specified in the URL is down, the RPG cannot establish a connection with the cluster. To mitigate this scenario, you can enter multiple URLs, allowing the RPG to establish a connection with more than one node.

After you drag an RPG onto the canvas, you can configure settings of the RPG or delete the RPG. To configure settings, double-click on the RPG, or right-click on the RPG and select Configure from the context menu. To delete an RPG, right-click on the processor and select Delete from the context menu, or highlight the RPG and select DELETE on your keyboard. The following image shows the Configure and Delete options in the context menu:



## Funnel

Funnels are used to combine data from many connections into a single connection. If many connections are created with the same destination, the canvas can become cluttered if those connections have to span a large space. By funneling these connections into a single connection, that single connection can then be drawn to span that large space instead.

To delete a funnel, right-click on the funnel and select Delete from the context menu, or highlight the funnel and select DELETE on your keyboard.

## Configuring a processor in CEM


Learn how to configure a processor using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

## Procedure

1. To configure a processor, right-click on the processor and select the Configure option.

Alternatively, just double-click on the processor.

The Configuration dialog opens as shown in the following image:



The Configuration dialog contains the following sections:

- Settings. The Settings section contains the following configuration items:

Properties	Description
Processor Name	Allows you to change the name of the processor. The name of a processor by default is the same as the processor type.
Penalty Duration	The amount of time used when a processor penalizes a FlowFile. During the normal course of processing a piece of data (a FlowFile), an event might occur that indicates that the data cannot be processed at this time but the data might be processable at a later time. When this occurs, the processor might choose to penalize the FlowFile. This prevents the FlowFile from being processed for some period of time. For example, if the processor needs to push the data to a remote service, but the remote service already has a file with the same name as the filename that the processor is specifying, the processor might penalize the FlowFile. The penalty duration allows you to specify how long the FlowFile must be penalized. The default value is 30,000 milliseconds.
Yield Duration	When a processor yields, the amount of time that elapses before the processor is re-scheduled is the yield duration. A processor might determine that some situation exists such that the processor can no longer make any progress, regardless of the data that it is processing. For example, if a processor needs to push data to a remote service and that service is not responding, the processor cannot make any progress. As a result, the processor must yield, which prevents the processor from being scheduled to run for some period of time. The default value is 1,000 milliseconds.



Properties	Description
Automatically Terminated Relationships	Each of the relationships that is defined by the processor is listed here. In order for a processor to be considered valid, each relationship defined by the processor must be either connected to a downstream component or auto-terminated. If a relationship is auto-terminated, any FlowFile that is routed to that relationship is removed from the flow and its processing is considered as complete.


- Scheduling. The Scheduling section contains the following configuration items:

Properties	Description
Scheduling Strategy	There are two options for scheduling components: <ul style="list-style-type: none"> <li>• Timer Driven. This is the default mode. The processor is scheduled to run on a regular interval. The interval at which the processor runs is defined by the Run Schedule option (see below).</li> <li>• Event Driven. When this mode is selected, the processor is triggered to run by an event, and that event occurs when FlowFiles enter connections feeding this processor. This mode is currently considered experimental and is not supported by all processors. When this mode is selected, the Run Schedule option is not configurable, as the processor is not triggered to run periodically but as the result of an event.</li> </ul>
Concurrent Tasks	This controls how many threads the processor uses or how many FlowFiles must be processed by this processor at the same time. Increasing this value allows the processor to handle more data in the same amount of time. However, it does this by using system resources that then are not usable by other processors. This essentially provides a relative weighing of processors. For example, it controls how much resources of the system must be allocated to this processor instead of other processors. This field is available for most processors. There are, however, some types of processors that can only be scheduled with a single concurrent task.
Run Schedule	This dictates how often the processor must be scheduled to run. The valid values for this field depend on the selected scheduling strategy (see above). When you select the Event Driven scheduling strategy, this field is not available. When you select the Timer Driven scheduling strategy, this value is a time duration specified by a number followed by a time unit, for example, 1 second or 5 mins. A value of 0 second means that the processor must run as often as possible as long as it has data to process. This is true for any time duration of 0, regardless of the time unit (for example, 0 sec, 0 mins, 0 days).
Run Duration	This slider controls how long the processor must be scheduled to run each time it is triggered. When a processor finishes running, it must update the repository in order to transfer the FlowFiles to the next connection. Updating the repository is expensive, so the more work that can be done at once before updating the repository, the more work the processor can handle (higher throughput). However, this means that the next processor cannot start processing those FlowFiles until the previous process updates this repository. As a result, the latency (the time required to process the FlowFile from beginning to end) becomes longer. As a result, the slider provides a spectrum from which you can choose to favor Lower Latency or Higher Throughput.

- Properties. The Properties section provides a mechanism to configure processor-specific behavior. There are no default properties. Each type of processor must define which properties make sense for its use case.

A GenerateFlowFile processor, by default, has four properties including Batch Size, Data Format, File Size, and Unique FlowFiles. Next to the name of each property, there appears a small question-mark symbol (◦) indicating that additional information is available. Hovering over this symbol with the mouse provides

additional details about the property, the default value and whether Expression Language is supported. Here is an example of GenerateFlowFile processor with additional information for the Batch Size property:



The screenshot displays the Cloudera Edge Management (CEM) interface for configuring a processor. On the left, a sidebar shows navigation options: Monitor, Edge Events, Design (selected), and Agent Manager. The main design canvas is titled 'Design / Agent Class' and shows a 'minifi-java-latest' processor within a 'DESIGN PROCESSOR GROUP'. A tooltip for the 'Batch Size' property is visible, stating 'The number of FlowFiles to be transferred in each invocation'. The configuration panel on the right is titled 'GenerateFlowFile (Processor) Configuration' and includes a 'Run Duration\*' slider, a table of properties, and an 'About' section.

Property	Value
File Size	0B
Batch Size	1
Data Format	
Unique FlowFiles	Default value: 1
Custom Text	Expression language scope: Not Supported
Character Set	UTF-8

**About**


PROCESSOR ID  
29d1f678-10dd-411f-b5c2-5a3367ab11a4

PROCESSOR TYPE  
GenerateFlowFile 1.3.1


BUNDLE  
org.apache.nifi.minifi-minifi-standard-nar

Clicking on the value for the property allows you to change the value. Depending on the values that are allowed for the property, you are either provided a drop-down from which to choose a value, or a text area

to type a value. Here is an example of GenerateFlowFile processor with the drop-down for the Data Format property:





Each of the properties has an arrow in the row showing that they can be converted to parameters. The following image shows the Convert to parameter option for the Unique FlowFiles property:




For some processors, there appears an Add Property button, beside the Properties section, for adding a user-defined property. When you click this button, a dialog opens, which allows you to enter the name and value of a new property. Not all processors allow user-defined properties. The RouteOnAttribute processor, however,

allows user-defined properties. In fact, this Processor will not be valid until you add a property. The following image shows the Add Property button in the Configuration dialog of the RouteOnAttribute processor:



**Note:** After a user-defined property has been added, a trash icon (  ) appears on the right-hand side of that row. You can remove the user-defined property from the processor by clicking the trash icon.

- About. The About section provides the Processor ID, Processor Type, and Bundle details of the processor, as shown in the following image:



- Comments. This tab simply provides an area for you to include whatever comments are appropriate for this component.
2. After you configure a processor, click the Apply button to apply the changes.


## Configuring a remote process group in CEM

Learn how to configure a remote process group using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure

1. To configure an RPG, right-click on the RPG and select the Configure option.

Alternatively, just double-click on the RPG. The Configuration dialog opens as shown in the following image:



The Configuration dialog contains the following two sections:

- Settings
  - About. The About section provides the Remote Process Group ID.
2. Configure the following properties in Settings section:

Properties	Description
URL	Allows you to change the URL of the RPG.
Transport Protocol	There are two options for transport protocol: <ul style="list-style-type: none"> <li>• RAW. This is the default protocol which uses raw socket communication by using a dedicated port.</li> <li>• HTTP. The HTTP transport protocol is useful if the remote NiFi instance is in a restricted network that only allows access through HTTP(S) protocol or only accessible from a specific HTTP Proxy server.</li> </ul>
Local Network Interface	In some cases, it might be desirable to prefer one network interface over another. For example, if a wired interface and a wireless interface exist, the wired interface might be preferred. This can be configured by specifying the name of the network interface to use in this box. If the value entered is not valid, the Remote Process Group will not be valid and will not communicate with other NiFi instances until this is resolved.
HTTP Proxy Server Hostname	Specify the host name of the proxy server, if you select HTTP transport protocol.
HTTP Proxy Server Port	Specify the port number of the proxy server, if you select HTTP transport protocol.

Properties	Description
Communications Timeout	When communication with the RPG takes longer than this amount of time, it will timeout. The default value is 30 seconds.
Yield Duration	When communication with the RPG fails, it will not be scheduled again until this amount of time elapses. The default value is 10 seconds.

- After you configure an RPG, apply the changes by clicking the Apply button.


## Adding services in CEM

Services are shared services that can be used by processors and other services to utilize for configuration or task execution. Learn how to add services using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure


- To add a service, click the SERVICES button at the bottom-left corner of the canvas, or simply right-click on the canvas and select Services.

The Services window opens as shown in the following image:



2. Click the ADD SERVICE button.

The Add Service dialog opens. It provides a list of the available services as shown in the following image:




3. Select the service you want to add and click Add, or simply double-click on the name of the service to add it. You can also use the Filter items field at the top-right corner of the window to search for the desired service by name.

4.

After you add a service, configure it by clicking the Configure icon (  ) in the far-right column.

The Configuration dialog opens as shown in the following image:




The Configuration dialog contains the following sections:

- **Settings.** The Settings section provides a place for you to give the service a unique name. The name of a service by default is the same as the service type.
- **Properties.** The Properties section lists the various properties that apply to the particular service. You can hover over the question mark icons with the mouse to see more information about each property.
- **About.** The About section provides the Service ID, Service Type, and Bundle details of the service.
- **Comments.** The Comments section is just an open-text field, where you can include comments about the service.

5. After you configure a service, click the Apply button to apply the configuration



If you want to delete a service, click the trash icon (  ) in the far-right column. To return to the canvas, click the BACK TO FLOW link.

## Connecting components in CEM


After you add processors and other components to the canvas of the Edge Flow Manager (EFM) UI and configure them, the next step is to connect them to one another. This is accomplished by creating a connection between each component.



### Procedure

1. Hover the mouse over a component.

An arrow appears as shown in the following image:



2. Drag the arrow from one component to another until the second component is highlighted, then release the mouse. A Create Connection dialog appears as shown in the following image:



The dialog allows you to choose the Source Relationship that must be included in the connection. At least one relationship must be selected. If only one relationship is available, it is automatically selected.

3. Select Add to create the connection.



**Note:** It is possible to draw a connection so that it loops back on the same processor. This can be useful if you want the processor to try to re-process flow files if the flow files go down a failure relationship. To create this type of looping connection, simply drag the connection arrow away and then back to the same processor until it is highlighted. Then release the mouse and the same Create Connection dialog, referenced earlier, appears.


## Configuring a connection in CEM

After you create a connection, you can change the configuration properties of the connection or move the connection using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

## Procedure

1. To change the configuration of a connection, right-click on the connection and select the Configure option, or double-click on the connection.

The Configuration dialog opens as shown in the following image:



The Configuration dialog contains the following two sections:

- Settings
  - About. The About section provides the Connection ID.
2. Configure the following properties in the Settings section:

Property	Description
Source Relationship	Allows you to change the Source Relationships of the connection.
Flowfile Expiration	FlowFile expiration is a concept by which data that cannot be processed in a timely fashion can be automatically removed from the flow. This is useful, for example, when the volume of data is expected to exceed the volume that can be sent to a remote site. The expiration period is based on the time that the data entered the MiNiFi instance. In other words, if the file expiration on a given connection is set to 1 hour, and a file that has been in the MiNiFi instance for one hour reaches that connection, it will expire. The default value is 60 seconds. A value of 0 seconds indicates that the data will never expire.
Back Pressure Object Threshold	This is the number of FlowFiles that can be in the queue before back pressure is applied. The default value is 0.
Back Pressure Size Threshold	This specifies the maximum amount of data (in size) that must be queued up before applying back pressure. The default value is 10,000 Bytes.
Connection Name	This field allows you to change the name of the connection. It is blank by default.

3. After you configure a connection, click the Apply button to apply the changes.


## Bending connections in CEM

Learn how to bend a connection using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure

1. To add a bend point (or elbow) to an existing connection, simply double-click on the connection in the spot where you want the bend point to be.
2. Use the mouse to grab the bend point and drag it so that the connection is bent in the desired way.

The following image shows a bend point in the connection between GenerateFlowFile and LogAttribute processors:



You can add as many bend points as you want. You can also use the mouse to drag and move the label on the connection to any existing bend point. To remove a bend point, simply double-click on it again.


## Refreshing a dataflow in CEM

Learn how to refresh a dataflow using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure

To refresh a flow that you monitor, right-click on the canvas and select Refresh.

The following image shows the Refresh option:



## Publishing a dataflow in CEM

Learn how to publish a dataflow using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### About this task





**Note:** Publishing is an asynchronous process and agents update their flow as they periodically heartbeat to the CEM server.

### Procedure

1. To publish a dataflow and make it available to all agents associated with its class, select Publish from the ACTIONS drop-down menu on the canvas.

The Publish Flow dialog appears as shown in the following image:

2. Enter comments if desired, and click Publish.

The flow status changes from modified (  ) to current (  ).

## Reverting a dataflow in CEM



Learn how to revert a dataflow using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Procedure

1. To remove all changes that you made since a flow was published, select Revert to last published from the ACTIONS drop-down menu on the canvas.

The Revert to last published version dialog appears as shown in the following image:

2. Select Revert to complete the process.

The flow status changes from modified (  ) to current (  ).


## Example dataflow in CEM

The example dataflow consists of just two processors: GenerateFlowFile and LogAttribute. These processors are normally used for testing, but they can also be used to build a ReadyFlow and see Cloudera Edge Management (CEM) in action.

### Procedure

1. Drag the GenerateFlowFile and LogAttribute processors to the canvas and connect them (using the guidelines provided above).

The dataflow appears on the canvas as shown in the following image:




2. Configure the GenerateFlowFile processor and click Apply to apply the changes.
  - In the Scheduling section, set Run Schedule to: 5 sec. Note that the GenerateFlowFile processor can create many FlowFiles very quickly. Therefore, setting the Run Schedule is important, so that the flow does not overwhelm the system CEM is running on.
  - In the Properties section, set File Size to 10 KB.

The following image shows the configuration properties of the GenerateFlowFile processor:

- Configure the LogAttribute processor and click Apply to apply the changes.
  - In the Settings section, under Automatically Terminated Relationships, select the checkbox next to success. This terminates flow files after the processor successfully processes them.
  - In the Properties section, set the Log Payload property to true. This way, the payload of the FlowFile is logged, in addition to its attributes. Otherwise, if set to false, just the attributes are logged.

The following image shows the configuration properties of the LogAttribute processor:



- Publish the flow by selecting Publish from the ACTIONS drop-down.



## Managing flow versions

Learn how to undo and redo changes in your draft dataflows, view and load published flow versions, and switch between versioned flows using the Edge Flow Manager (EFM) UI in Cloudera Edge Management (CEM).

### Undo/redo draft changes

You can undo changes in the CEM Flow Designer made after the last publish event, allowing you to revert accidental edits. Similarly, you can redo changes that were previously reverted.

#### Procedure

- Locate the Undo/Redo icons at the bottom right corner of the Flow Designer.
- Click  to revert changes made since the last flow publish event, or click  to reapply changes that were previously undone.



**Note:** These functions do not affect the Flow Parameters functionality.

### Switch between published flow versions

You can view and load previously published flow versions in the CEM Flow Designer.

## Procedure

### 1. View published flow versions.

- a) Open the right-side navigation pane when no component is selected.
- b) Review the list of previously published versions.

Each entry includes basic information like the publish date, publisher, and any comments added while publishing the flow.

### 2. Load a previous flow version.

- a) In the right-side navigation pane, find the version you want to load.
- b) Click the Load into flow designer option on the selected line.

This action replaces the current flow and parameters in the designer with the selected version.



**Note:** Loading a previous flow version into the Flow Designer does not automatically publish it. If you want to deploy the selected version to the agents, you need to do it manually using Flow Options Publish .

## Managing resources

Resource Manager in the Edge Flow Manager (EFM) UI extends the Asset Push functionality. It allows you to manage existing assets and extensions, upload new assets and extensions, assign them to selected agent classes, and deploy new MiNiFi extensions or ML models at runtime.

Unlike Asset Push, Resource Manager works for both new and offline agents, ensuring they receive the new files. It functions in secure and unsecure environments as well. For secure environments, establish a secure connection between EFM and the agents. For more information about setting up a secure connection, see *TLS configuration for CEM*.

All resources are listed on the **Resource Manager** page. When you upload a new resource , it is automatically synchronized between the EFM nodes. Only users with an Operator role can upload and delete resources, or assign them to agent classes.

Resource Manager

✕ Clear all
Add New Resource
REFRESHED: 50 seconds ago

Name ↑	File Name	Size	Type	Relative Path	Created	Uploaded By	Notes
Screenshot 2024-07-08 a...	Screenshot 2024-07-08 a...	4.89 KB	Asset		2024-07-09 09:06 CEST	Olivia Operator	
big file	imager_1.8.5.dmg	63.08 MB	Asset		2024-07-09 09:28 CEST	Admin EFM	
debug (3).tar.gz	debug (3).tar.gz	56.32 KB	Asset	log	2024-07-09 08:48 CEST	Admin EFM	debug log
debug (8).tar.gz	debug (8).tar.gz	446.72 KB	Extension		2024-07-09 09:04 CEST	Admin EFM	
minifi-standard-nar-2.24...	minifi-standard-nar-2.24...	73.21 MB	Asset		2024-07-09 10:17 CEST	Admin EFM	

Items per page:  1 - 5 of 5

You can edit the name of an existing resource, and download or delete it using the pop-up menu at the end of each resource row.

Name ↑	File Name	Size	Type	Relative Path	Created	Uploaded By	Notes
debug (1).tar.gz	debug (1).tar.gz	36.46 KB	Asset		2024-07-10 09:40 CEST	Admin EFM	

Items per page:  1

- Download
- Edit
- Delete

Click Add New Resource to upload new resources. In the **Add New Resource** pop-up, you can upload a single file or a batch of files at once. If you upload one file at a time, you can change its name. For batch uploads, you can only edit file names one by one from the **Resource Manager** page.


Specify the agents' resource location using the Relative path on the agent field. This is relative to the path set with the `efm.resourcemanager.repositoryPath` property.

You can upload assets or extensions. Agents will start to download the new resources after their next heartbeat. If a download fails, the agent will retry the download in the next heartbeat iteration. On the agent, assets are downloaded to the asset directory, and extensions are downloaded to the extensions directory within the agent's base path.



**Add New Resource** ✕

**File**

  
**Select File**  
Drop file or browse

**Name** 0/255

Override filename

**Resource Type**

Asset ▼

- Asset
- Extension

**Notes** 0/4K

Notes for this resource

**Add** **Cancel**

## Resources tab

The **Resources** tab is available on the agent class details page, if the class contains agents that are compatible with resource assignment.

On this tab, you can see all assigned resources and assign new ones.

The screenshot shows the Cloudera Edge Management dashboard. On the left is a navigation sidebar with options like Monitor, Edge Events, Design, Agent Manager, Resource Manager, and Administration. The main area is titled 'Dashboard' and contains a search bar and a list of agent classes. One class, 'nifi-minifi-java-2.24.08.0-5', is selected and highlighted. To the right of this class, there are tabs for 'Metrics', 'Alerts', and 'Resources', with 'Resources' being the active tab. Below the tabs, there is an 'Assigned Resources' section with a table of resources and an 'Assign Resource' button. The table has columns for Name, File Name, Size, Type, Relative Path, Created, Uploaded By, and Notes. At the bottom of the dashboard, there are 'Save' and 'Discard Changes' buttons.

Click Assign Resource to see and select available resources for assignment.



**Note:** Clicking the Assign button does not immediately synchronize the newly selected resources to the agents.

The 'Assign Resources' dialog box is shown. It has a title bar with a close button (X). Below the title bar are several filter buttons: Name, Filename, Type, Uploaded By, and Notes, along with a 'Clear all' button. The main area contains a table with the following columns: Name, File Name, Size, Type, Relative Path, Created, Uploaded By, and Notes. The table lists three resources: 'minifi-standard-nar...', 'big file', and 'Screenshot 2024-07...'. Each row has a checkbox in the 'Name' column. At the bottom of the dialog, there is an 'Items per page' dropdown set to '10', a page indicator '1 - 3 of 3', and navigation arrows. At the very bottom are 'Assign' and 'Cancel' buttons.

To start downloading the selected resources to the agents, you have to save the new assignments on the agent class details page. You can review and modify the new assignment before saving.



REFRESHED: 19 seconds ago

✔ nifi-minifi-java-2.24.08.0-5

3 Agents

Actions ▾

Metrics Alerts Resources

Assigned Resources

Assign Resource ⊕

Name ↑	File Name	Size	Type	Relative Path	Created	Uploaded By	Notes
debug ...	deb...	36.46 KB	Asset		7/10/24	Admin EFM	<span>New</span> ↻
debug ...	deb...	42.32 KB	Asset		7/10/24	Admin EFM	<span>New</span> ↻
debug ...	deb...	56.32 KB	Asset		7/10/24	Admin EFM	⊖
debug ...	deb...	56.32 KB	Asset		7/10/24	Admin EFM	⊖
debug ...	deb...	20.68 KB	Asset		7/10/24	Admin EFM	⊖

Save Discard Changes


### Resource management properties

You can find here the key resource management properties, which help configure synchronization, caching, and operational parameters, ensuring smooth and efficient management of resources across nodes and agents.

Property name	Default value	Description
efm.resourcemanager.resourceManagerPort	9010	Port for the resource synchronization endpoint
efm.resourcemanager.nodeAliveTtl	5 sec	Time-to-live after which a node is considered unavailable
efm.resourcemanager.resourceSynchronizationTriggerInterval	5 sec	Interval at which resource synchronization between nodes is triggered
efm.resourcemanager.nodeResourceCacheUpdateTriggerInterval	10 sec	Interval at which the resource list cache of the nodes is updated
efm.resourcemanager.repositoryPath	resources	Path to repository where EFM stores uploaded resources
efm.resourcemanager.blockSyncResourceReTriggerDuration	10 minutes	Duration for which EFM blocks re-triggering the SYNC RESOURCE operation
efm.operation.monitoring.rollingOperationsSize.sync.resolve	100	Maximum number of resources sent to agents at once

### Monitoring deployments in CEM

Learn the options, available in the Dashboard screen, that enable you to monitor C2 server and agent deployments. The Dashboard is the initial page in the Edge Flow Manager (EFM) UI.

Click the Monitor icon () to navigate to the Dashboard screen as shown in the following image:

Dashboard

Search by class name

Status	Class Name ↑	Number of Agents	Last Flow Updated	Updated Agents
Good Health	minifi-cpp-1.21.02.0-19	1	No flow has been published	>
Good Health	minifi-cpp-latest	3	No flow has been published	>
Good Health	minifi-java-1.2.2.2	1	No flow has been published	>
Good Health	minifi-java-latest	3	No flow has been published	>
Unknown Health	Unassigned	0	No flow has been published	>

Items per page: 10 1 - 5 of 5 < >

CEM provides the following details for deployments:

- Status
  - Good Health: Recent heartbeats are received from all of the agents in the agent class.
  - Concerning Health: Some of the agents did not send heartbeat for the time period defined in the `efm.monitor.maxHeartbeatInterval` property.
  - Bad Health: None of the agents sent heartbeats in the given class for the time period defined in the `efm.monitor.maxHeartbeatInterval` property.
  - Unknown Health: Agents for this class may have not yet registered or heartbeat intervals cannot be determined.
- Class Name
- Number of Agents
 

The count of assigned agents (Online + Missing) to the given agent class.
- Last Flow Updated
 

The time of the latest flow update of the given agent class.
- Updated Agents
 

Shows the current status of the last batched command, for example, flow publish, property update. While there are missing agents in a class, batched commands can not fully complete.
- Arrow icon
 

Click the arrow icon to fetch more details about the deployment. You can monitor metrics and alerts details for your deployment in two different tabs.

### Monitoring class details in the Metrics tab

Click the arrow icon in the Dashboard page to fetch more details for your deployment. The Metrics tab appears as shown in the following image:

The Metrics tab displays the following details:

- Information

This section displays details about the class including flow ID, latest flow version, and Grafana dashboard link if you enabled it. For more information, see *Monitoring Metrics with Grafana*.

- Repositories (Class Average)

Usage details of the repositories of the agents in the agent class.

- Connection Queues (Class Average)

Aggregate views of all the connections throughout the agents in the selected class.

### Monitoring alert details in the Alerts tab

The Alerts tab displays the alert messages associated with the agent class.

Click the arrow icon in the Dashboard page, and then go to the Alerts tab to fetch alert messages along with the time they are raised at for your deployment, as shown in the following image:

Dashboard / Agent Class

Search by class name

Status	Class Name ↑
Good Health	minifi-cpp-1.21.02.0-19
Bad Health	minifi-cpp-latest
Good Health	minifi-java-1.2.2.2
Good Health	minifi-java-latest
Unknown Health	Unassigned

minifi-cpp-latest  
3 Agents

Metrics Alerts

Displaying alerts from the past hour. View all alerts.

Alert Message	Alert Time
Agent Is Online	2022-04-23 11:23 IST
Agent Is Online	2022-04-23 11:23 IST
Agent Is Online	2022-04-23 11:23 IST
Operation With ID F4ea7168-D90e-4edf-9cd9-Ad74fcd66c47 Failed. Details: ...	2022-04-23 11:22 IST
Operation With ID 6d698572-964b-4125-8326-F2e543cd5693 Failed. Details: ...	2022-04-23 11:22 IST
Operation With ID 278b998d-3cac-4b4e-9b82-F7b142969f9d Failed. Details: ...	2022-04-23 11:22 IST
Agent Is Missing	2022-04-23 11:21 IST
Agent Is Missing	2022-04-23 11:21 IST
Agent Is Missing	2022-04-23 11:21 IST
Agent Is Online	2022-04-23 11:16 IST
Agent Is Online	2022-04-23 11:16 IST
Agent Is Online	2022-04-23 11:16 IST
Operation With ID C36612eb-165e-4a38-AcF1-67d1d71b4a8 Failed. Details: ...	2022-04-23 11:15 IST
Operation With ID 89e47d60-A874-4a41-984c-4a02adb1a71d Failed. Details: ...	2022-04-23 11:15 IST
Operation With ID 66d15ba5-110e-45cc-8153-Cee0c44e4f93 Failed. Details: ...	2022-04-23 11:15 IST
Agent Is Missing	2022-04-23 11:15 IST

You can scroll through the alerts to see more alerts in the system. Each alert has an arrow beside it, and you can click it to fetch more details about that alert.

Click the View all alerts link to navigate to the Edge Events page which is filtered by alert event type, as shown in the following image:

Edge Events

Event Type: Alert × Class Name: minifi-java-latest × Filter by: Severity

Date/Time ↓	Severity	Event Type	Message	Class Name	Source Type	Event Source ID
2022-04-13 08:25 CEST	WARN	Alert	Agent is missing	minifi-java-latest	Agent	ffb5baaa-02d3-455...
2022-04-13 08:25 CEST	WARN	Alert	Agent is missing	minifi-java-latest	Agent	5f43eba2-72c2-4ee...
2022-04-13 08:25 CEST	WARN	Alert	Agent is missing	minifi-java-latest	Agent	4a955dd1-a687-44...

Time range: All Rows per page: 20 1 - 3 of 3

## Actions button

Agent class level commands can be initiated through this option.

The screenshot displays the Cloudera Edge Management (CEM) interface. On the left is a dark sidebar with navigation options: Monitor, Edge Events, Design, and Agent Manager. The main area is titled 'Dashboard / Agent Class' and contains a search bar and a table of agent classes. The table lists 'minifi-cpp-1.21.02.0-19' (Good Health), 'minifi-cpp-latest' (Bad Health), 'minifi-java-1.2.2.2' (Good Health), 'minifi-java-latest' (Good Health), and 'Unassigned' (Unknown Health). The 'minifi-cpp-latest' class is selected, showing a detailed view on the right. This view includes an 'Information' section with 'FLOW ID' (5c964a49-86b1-427b-b9d3-466b56605a9c) and 'FLOW VERSION' (1). Below this is a 'DASHBOARD' section with a 'View Grafana Dashboard' link. The 'Repositories (Class Average)' section shows 'FlowFile' and 'Provenance' as 'Unknown'. The 'Connection Queues (Class Average)' section shows 'No connection queues to display.' A 'Manage Agents' button is visible in the top right corner of the detailed view.

Status	Class Name ↑
Good Health	minifi-cpp-1.21.02.0-19
Bad Health	minifi-cpp-latest
Good Health	minifi-java-1.2.2.2
Good Health	minifi-java-latest
Unknown Health	Unassigned

**minifi-cpp-latest**  
3 Agents

**Information**

FLOW ID	5c964a49-86b1-427b-b9d3-466b56605a9c	FLOW VERSION	1
---------	--------------------------------------	--------------	---

**Repositories (Class Average)**

NAME: FlowFile	NAME: Provenance
Unknown	Unknown

**Connection Queues (Class Average)**

No connection queues to display.

- Edit Agent Configuration

The Edit Agent Configuration action enables you to change a range of agent properties using EFM.



**Note:** In a secure environment, the Edit Agent Configuration action is only available to users that have the Operator role assigned to them on the agent class. For more information, see *Policies for agent class roles*. Additionally, the action is only supported with the following agent versions:

- minifi-cpp 1.22.04 or higher
- minifi-java 1.23.02 or higher

Click **Actions** **Edit Agent Configuration** . The Edit Agent Configuration dialog appears:

Edit Agent Configuration
✕

⚠ All agents in this class must be restarted for a new configuration to take effect. New property values are applied to all agents.

CLASS NAME	NUMBER OF AGENTS
minifi-cpp-latest	3

Property Name

minifi.disk.space.watchdog.enable
▼

Value

⊕ Add

No Properties to display.

Cancel
Apply

Select a property which you want to update in the Property Name field, provide the desired value for that property in the Value field, and click Apply.

You can also update multiple properties at the same time. To do so, use the Add button and repeat the previous steps.



**Note:** If you edit the agent class name, take into consideration that leading and trailing whitespaces are accepted for Agent Class names.

The command is sent to the agents only after you click the Apply button. All agents in the agent class are notified about the required updates in their next heartbeat, so updating the values depends on the heartbeat interval configured. The status of the ongoing property update command can be followed in the Dashboard view.

You can see that property update is possible only on class level (not individual agent level). This is because Cloudera wants to enforce configuration consistency between the agents under the same agent class. To read about how to view a specific agent's configuration, see *Configuration tab* section in *Agent details in CEM*.

- Manage Agents

To get the list of agents assigned to the current agent class, click the Manage Agents option from the Actions dropdown. For more details about how to manage agents, see *Managing agents in CEM*.



## Related Information

[Monitoring metrics in CEM with Grafana](#)

[Policies for agent class roles](#)


[Agent details in CEM](#)

[Managing agents in CEM](#)

# Monitoring events in CEM

Learn the options, available in the Edge Events screen, that enable you to monitor C2 server and agent events.

Click the Edge Events icon (  Edge Events ) to navigate to the Edge Events screen.



Date/Time ↓	Severity	Event Type	Message	Class Name	Source Type	Event Source ID
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">4a955dd1-a687-44...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">5f43eba2-72c2-4ee...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">ffb5baaa-02d3-455...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-1.2.2.2</a>	Agent	<a href="#">a3217be3-bee8-41...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39e114ee-ba7a-11...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39d18a6a-ba7a-11...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39741e70-ba7a-11...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-1.21.02...</a>	Agent	<a href="#">48694392-ba7a-11...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">4a955dd1-a687-44...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">5f43eba2-72c2-4ee...</a>
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">ffb5baaa-02d3-455...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-1.2.2.2</a>	Agent	<a href="#">a3217be3-bee8-41...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39e114ee-ba7a-11...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39d18a6a-ba7a-11...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-latest</a>	Agent	<a href="#">39741e70-ba7a-11...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-cpp-1.21.02...</a>	Agent	<a href="#">48694392-ba7a-11...</a>
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	<a href="#">minif-java-latest</a>	Agent	<a href="#">4a955dd1-a687-44...</a>

The Edge Events screen provides the following details for events:

- Date/Time
- Severity
- Event Type
- Message
- Class Name
- Source Type
- Event Source ID

The Class Name and Event Source ID fields also act as links. If you click a class name link, the Metrics tab for that class appears and helps you to track details and alerts for that class, as described in the *Monitoring deployments in CEM*. If you click an event source ID link, the Metrics tab for that event appears and helps you to track details, alerts, commands, and configurations for that event, as described in the *Managing agents in CEM*.

You can display events based on time range (All, Last Hour, Last 4 Hours, Last 24 Hours, Last 7 Days) by selecting the desired value in the Time range drop-down. The number of rows displayed (20, 50, 100) can be configured by selecting the desired value from the Rows per page drop-down. The following image shows the Time range and Rows per page options in the UI:

The screenshot shows the 'Edge Events' page in Cloudera Edge Management. The left sidebar contains navigation options: Monitor, Edge Events (selected), Design, and Agent Manager. The main content area displays a table of events. At the top right, there is a search filter box and a dropdown menu set to 'Severity'. The table has columns for Date/Time, Severity, Event Type, Message, Class Name, Source Type, and Event Source ID. The events listed are all 'Heartbeat Received' with a 'DEBUG' severity, occurring on 2022-04-13 at 05:59 CEST. The Class Name column includes entries like 'minifi-java-latest', 'minifi-cpp-latest', and 'minifi-cpp-1.21.02...'. The Event Source ID column shows various alphanumeric identifiers. At the bottom of the table, there is a 'Time range' dropdown set to 'All', 'Rows per page' set to '20', and a pagination indicator '1 - 20 of 80'.

Date/Time	Severity	Event Type	Message	Class Name	Source Type	Event Source ID
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	5f43eba2-72c2-4ee...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	ffb5baaa-02d3-455...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-1.2.2.2	Agent	a3217be3-bee8-41...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39e114ee-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39d18a6a-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39741e70-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-1.21.02...	Agent	48694392-ba7a-11...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	5f43eba2-72c2-4ee...
2022-04-13 05:59 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	ffb5baaa-02d3-455...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-1.2.2.2	Agent	a3217be3-bee8-41...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39e114ee-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39d18a6a-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-latest	Agent	39741e70-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-cpp-1.21.02...	Agent	48694392-ba7a-11...
2022-04-13 05:58 CEST	DEBUG	Heartbeat Received	Heartbeat received.	minifi-java-latest	Agent	4a955dd1-a687-44...

## Sorting and filtering

You can sort data in each column in ascending or descending order by clicking the column name. For example, you can sort the events based on class by clicking the Class Name column.

You can also filter the events by Date/Time, Severity, Event Type, Message, Class Name, Source Type, and Event Source ID. Select the column name in the drop-down box at the top-right corner of the UI, enter the filter value, and select RETURN on the keyboard to apply the filter.

You can use multiple column names and filter values to filter your data. Here is an example of filtering by Event Type and Source Type:

The screenshot shows the 'Edge Events' page with filters applied: 'Event Type: Alert' and 'Source Type: Agent'. The search filter box is empty. The table displays filtered events with a 'WARN' severity and 'Alert' event type, all with the message 'Agent is missing'. The Class Name column shows 'minifi-cpp-latest' for all events. The Event Source ID column shows various alphanumeric identifiers. At the bottom of the table, there is a 'Time range' dropdown set to 'All', 'Rows per page' set to '20', and a pagination indicator '1 - 20 of 673'. A status bar at the bottom left indicates '2771 new edge events available' and 'Reload or Show Latest'.


Date/Time	Severity	Event Type	Message	Class Name	Source Type	Event Source ID
2022-04-22 06:15 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49dfbcf2-bbdc-1...
2022-04-21 20:48 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49dfbcf2-bbdc-1...
2022-04-21 19:15 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-22 00:55 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49cb3c1e-bbdc-1...
2022-04-22 07:15 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49dfbcf2-bbdc-1...
2022-04-22 01:08 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-22 12:28 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-22 09:48 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-22 01:48 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-21 20:01 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49cb3c1e-bbdc-1...
2022-04-21 22:22 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49dfbcf2-bbdc-1...
2022-04-22 05:28 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49cb3c1e-bbdc-1...
2022-04-22 01:28 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	49cb3c1e-bbdc-1...
2022-04-21 19:22 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-22 02:42 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...
2022-04-21 22:08 IST	WARN	Alert	Agent is missing	minifi-cpp-latest	Agent	4a0edf46-bbdc-1...

After you filter the event details as per your requirement, you can share the URL with other users who can then view your filtered event list.


### Reload and show latest


You can view new events in the system by selecting either the Reload or Show Latest link which appears after you spend some time in the Edge Events page. Reload refreshes events using the existing search and sort criteria. Show Latest reloads events but sorts by the latest events using the existing search criteria.

The following image shows the Reload and Show Latest links in the Edge Events screen:



### Event details

You can find the details of events by clicking the edge event details icon (  ) beside each event. The following image shows event details of the event selected in the Edge Events section:



### Related Information

[Monitoring deployments in CEM](#)

[Managing agents in CEM](#)

## Monitoring metrics in CEM with Grafana

Cloudera Edge Management (CEM) can export time series metrics to several metric storage providers. The recommended metrics store service is Prometheus. Prometheus integrates with Grafana for time series metric visualization. With Prometheus and Grafana, you can store and visualize metrics for CEM.

You need to perform the following tasks before you start visualizing CEM metrics with Prometheus and Grafana.

### Enabling Prometheus metrics in CEM

Ensure that the following metrics exporting property is enabled in CEM in the `efm.properties` file:

```
management.metrics.export.prometheus.enabled=true
```

You need to customize the following `efm.dashboard.*` properties:

```
efm.dashboard.base-url=http://grafana.example.com:3000
efm.dashboard.url.agentclass=/d/efm-agent-class/?var-agentClass={agentClass}
```

The base-url must reflect the location where you host Grafana. For details, see the *Setting up Grafana* section.

The dashboard URLs must point to the locations where you have set up agent and agent class specific URLs (see below).

### Setting up Prometheus

1. Install Prometheus on a host that has network connectivity to CEM. For instructions about how to install Prometheus, see <https://prometheus.io>.
2. Configure your `prometheus.yml` file to scrape the CEM instance. For example:

```
# Global config
```

```
global:
  scrape_interval: 1m
  evaluation_interval: 1m
```

# The following is a scrape configuration for CEM. Add this to any other scrape configurations you desire. In this example, it is Prometheus.

```
scrape_configs:
  - job_name: 'cem-efm'
    metrics_path: '/efm/actuator/prometheus'
    scrape_interval: 15s
    static_configs:
      - targets: ['efm.example.com:10090']
```

For additional scrape configuration properties, such as TLS settings, see the Prometheus configuration guide: [https://prometheus.io/docs/prometheus/latest/configuration/configuration/#scrape\\_config](https://prometheus.io/docs/prometheus/latest/configuration/configuration/#scrape_config).

3. Verify Prometheus configuration.

## Setting up Grafana

1. Install Grafana on a host that has network connectivity to Prometheus. For instructions about how to install Grafana, see <https://grafana.com>.
2. Configure Grafana to use Prometheus as a datasource. This can be done through the Grafana UI or through a data sources.yml provisioning file in conf/provisioning/datasources. For example:

```
# config file version
apiVersion: 1
```

# List of datasources to insert or update depending on what is available in the database:

```
apiVersion: 1

datasources:
- name: EFM Prometheus
  type: prometheus
  access: proxy
  orgId: 1
  url: http://prometheus.example.com:9090
  password:
  user:
  database:
  basicAuth: false
  basicAuthUser:
  basicAuthPassword:
  withCredentials: false
  isDefault: true
  jsonData:
    graphiteVersion: "1.1"
    tlsAuth: false
    tlsAuthWithCACert: false
  secureJsonData:
    tlsCACert: "..."
    tlsClientCert: "..."
    tlsClientKey: "..."
  version: 1
  editable: true
```

For more information about configuring a Prometheus datasource in Grafana, see <https://grafana.com/docs/features/datasources/prometheus/>.

3. Download the CEM Grafana dashboard templates.

You can download the Grafana dashboard templates from <https://github.com/cloudera/cloudera-edge-management-grafana-boards>.

4. Import each JSON dashboard through the Grafana UI. Follow the instructions provided in the following Grafana document: [https://grafana.com/docs/reference/export\\_import/#importing-a-dashboard](https://grafana.com/docs/reference/export_import/#importing-a-dashboard).

Alternatively, you can create a dashboards provider config file in conf/provisioning/dashboards to import dashboards.

```
apiVersion: 1

providers:
- name: 'efm-prometheus'
  orgId: 1
  folder: 'EFM Prometheus'
  type: file
  disableDeletion: false
  editable: true
  options:
```

```
path: /tmp/dashboards
```

Update the path property as per your requirements and also create the directory in the local filesystem. Place the downloaded dashboard definitions in the created directory and start Grafana.

CEM dashboards should now be available in the Grafana UI.

### **Navigating to Grafana dashboard in CEM**

To navigate to class specific Grafana dashboards, select a class in the Dashboard screen. The Metrics tab appears for the class. Select the View Grafana Dashboard link in the Information section.

For more information about the integration with Prometheus and Grafana, check out the video on the Cloudera Edge Management YouTube playlist: