

Hortonworks DataFlow

Administration

(June 6, 2018)

Hortonworks DataFlow: Administration

Copyright © 2012-2018 Hortonworks, Inc. Some rights reserved.



Except where otherwise noted, this document is licensed under
Creative Commons Attribution ShareAlike 4.0 License.
<http://creativecommons.org/licenses/by-sa/4.0/legalcode>

Table of Contents

1. NiFi System Administrator's Guide	1
1.1. NiFi System Administrator's Guide	1
1.1.1. Configuration Best Practices	1
1.1.2. Security Configuration	2
1.1.3. User Authentication	6
1.1.4. Multi-Tenant Authorization	10
1.1.5. Encryption Configuration	42
1.1.6. Encrypted Passwords in Configuration Files	49
1.1.7. Administrative Tools	54
1.1.8. Clustering Configuration	60
1.1.9. State Management	64
1.1.10. Bootstrap Properties	75
1.1.11. Notification Services	76
1.1.12. Proxy Configuration	79
1.1.13. Kerberos Service	80
1.1.14. System Properties	81

List of Tables

1.1. Table 1. Maximum Password Length on Limited Cryptographic Strength JVM 48

1. NiFi System Administrator's Guide

1.1. NiFi System Administrator's Guide

1.1.1. Configuration Best Practices

If you are running on Linux, consider these best practices. Typical Linux defaults are not necessarily well tuned for the needs of an IO intensive application like NiFi. For all of these areas, your distribution's requirements may vary. Use these sections as advice, but consult your distribution-specific documentation for how best to achieve these recommendations.

Maximum File Handles NiFi will at any one time potentially have a very large number of file handles open. Increase the limits by editing `/etc/security/limits.conf` to add something like

```
* hard nofile 50000
* soft nofile 50000
```

Maximum Forked Processes NiFi may be configured to generate a significant number of threads. To increase the allowable number edit `/etc/security/limits.conf`

```
* hard nproc 10000
* soft nproc 10000
```

And your distribution may require an edit to `/etc/security/limits.d/90-nproc.conf` by adding

```
* soft nproc 10000
```

Increase the number of TCP socket ports available This is particularly important if your flow will be setting up and tearing down a large number of sockets in small period of time.

```
sudo sysctl -w net.ipv4.ip_local_port_range="10000 65000"
```

Set how long sockets stay in a TIMED_WAIT state when closed You don't want your sockets to sit and linger too long given that you want to be able to quickly setup and teardown new sockets. It is a good idea to read more about it but to adjust do something like

```
sudo sysctl -w net.ipv4.netfilter.ip_conntrack_tcp_timeout_time_wait="1"
```

Tell Linux you never want NiFi to swap Swapping is fantastic for some applications. It isn't good for something like NiFi that always wants to be running. To tell Linux you'd like swapping off you can edit `/etc/sysctl.conf` to add the following line

```
vm.swappiness = 0
```

For the partitions handling the various NiFi repos turn off things like `'atime'`. Doing so can cause a surprising bump in throughput. Edit the `/etc/fstab` file and for the partition(s) of interest add the `'noatime'` option.

1.1.2. Security Configuration

NiFi provides several different configuration options for security purposes. The most important properties are those under the "security properties" heading in the *nifi.properties* file. In order to run securely, the following properties must be set:

Property Name	Description
<code>nifi.security.keystore</code>	Filename of the Keystore that contains the server's private key.
<code>nifi.security.keystoreType</code>	The type of Keystore. Must be either PKCS12 or JKS. JKS is the preferred type, PKCS12 files will be loaded with BouncyCastle provider.
<code>nifi.security.keystorePasswd</code>	The password for the Keystore.
<code>nifi.security.keyPasswd</code>	The password for the certificate in the Keystore. If not set, the value of <code>nifi.security.keystorePasswd</code> will be used.
<code>nifi.security.truststore</code>	Filename of the Truststore that will be used to authorize those connecting to NiFi. A secured instance with no Truststore will refuse all incoming connections.
<code>nifi.security.truststoreType</code>	The type of the Truststore. Must be either PKCS12 or JKS. JKS is the preferred type, PKCS12 files will be loaded with BouncyCastle provider.
<code>nifi.security.truststorePasswd</code>	The password for the Truststore.
<code>nifi.security.needClientAuth</code>	Set to true to specify that connecting clients must authenticate themselves. This property is used by the NiFi cluster protocol to indicate that nodes in the cluster will be authenticated and must have certificates that are trusted by the Truststores.

Once the above properties have been configured, we can enable the User Interface to be accessed over HTTPS instead of HTTP. This is accomplished by setting the `nifi.web.https.host` and `nifi.web.https.port` properties. The `nifi.web.https.host` property indicates which hostname the server should run on. If it is desired that the HTTPS interface be accessible from all network interfaces, a value of `0.0.0.0` should be used. To allow admins to configure the application to run only on specific network interfaces, `nifi.web.http.network.interface*` or `nifi.web.https.network.interface*` properties can be specified.

It is important when enabling HTTPS that the `nifi.web.http.port` property be unset.

Similar to `nifi.security.needClientAuth`, the web server can be configured to require certificate based client authentication for users accessing the User Interface. In order to do this it must be configured to not support username/password authentication using [Lightweight Directory Access Protocol \(LDAP\)](#) or [Kerberos](#). Either of these options will configure the web server to WANT certificate based client authentication. This will allow it to support users with certificates and those without that may be logging in with their credentials or those accessing anonymously. If username/password authentication and anonymous access are not configured, the web server will REQUIRE certificate based client authentication. See [User Authentication](#) for more details.

Now that the User Interface has been secured, we can easily secure Site-to-Site connections and inner-cluster communications, as well. This is accomplished by setting

the `nifi.remote.input.secure` and `nifi.cluster.protocol.is.secure` properties, respectively, to `true`.

1.1.2.1. TLS Generation Toolkit

In order to facilitate the secure setup of NiFi, you can use the `tls-toolkit` command line utility to automatically generate the required keystores, truststore, and relevant configuration files. This is especially useful for securing multiple NiFi nodes, which can be a tedious and error-prone process.

JKS keystores and truststores are recommended for NiFi. This tool allows the specification of other keystore types on the command line but will ignore a type of PKCS12 for use as the truststore because that format has some compatibility issues between BouncyCastle and Oracle implementations.

The `tls-toolkit` command line tool has two primary modes of operation:

1. Standalone - generates the certificate authority, keystores, truststores, and `nifi.properties` files in one command.
2. Client/Server mode - uses a Certificate Authority Server that accepts Certificate Signing Requests from clients, signs them, and sends the resulting certificates back. Both client and server validate the other's identity through a shared secret.

1.1.2.1.1. Standalone

Standalone mode is invoked by running `./bin/tls-toolkit.sh standalone -h` which prints the usage information along with descriptions of options that can be specified.

You can use the following command line options with the `tls-toolkit` in standalone mode:

- `-a,--keyAlgorithm <arg>` Algorithm to use for generated keys (default: RSA)
- `-B,--clientCertPassword <arg>` Password for client certificate. Must either be one value or one for each client DN (auto-generate if not specified)
- `-c,--certificateAuthorityHostname <arg>` Hostname of NiFi Certificate Authority (default: localhost)
- `-C,--clientCertDn <arg>` Generate client certificate suitable for use in browser with specified DN (Can be specified multiple times)
- `-d,--days <arg>` Number of days issued certificate should be valid for (default: 1095)
- `-f,--nifiPropertiesFile <arg>` Base `nifi.properties` file to update (Embedded file identical to the one in a default NiFi install will be used if not specified)
- `-g,--differentKeyAndKeystorePasswords` Use different generated password for the key and the keystore
- `-G,--globalPortSequence <arg>` Use sequential ports that are calculated for all hosts according to the provided hostname expressions (Can be specified multiple times, MUST BE SAME FROM RUN TO RUN)

- `-h,--help` Print help and exit
- `-k,--keySize <arg>` Number of bits for generated keys (default: 2048)
- `-K,--keyPassword <arg>` Key password to use. Must either be one value or one for each host (auto-generate if not specified)
- `-n,--hostnames <arg>` Comma separated list of hostnames
- `--nifiDnPrefix <arg>` String to prepend to hostname(s) when determining DN (default: CN=)
- `--nifiDnSuffix <arg>` String to append to hostname(s) when determining DN (default: , OU=NIFI)
- `-o,--outputDirectory <arg>` The directory to output keystores, truststore, config files (default: ../bin)
- `-O,--isOverwrite` Overwrite existing host output
- `-P,--trustStorePassword <arg>` Keystore password to use. Must either be one value or one for each host (auto-generate if not specified)
- `-s,--signingAlgorithm <arg>` Algorithm to use for signing certificates (default: SHA256WITHRSA)
- `-S,--keyStorePassword <arg>` Keystore password to use. Must either be one value or one for each host (auto-generate if not specified)
- `--subjectAlternativeNames <arg>` Comma-separated list of domains to use as Subject Alternative Names in the certificate
- `-T,--keyStoreType <arg>` The type of keystores to generate (default: jks)

Hostname Patterns:

- Square brackets can be used in order to easily specify a range of hostnames. Example: [01-20]
- Parentheses can be used in order to specify that more than one NiFi instance will run on the given host(s). Example: (5)

Examples:

Create 4 sets of keystore, truststore, nifi.properties for localhost along with a client certificate with the given DN:

```
bin/tls-toolkit.sh standalone -n 'localhost(4)' -C 'CN=username,OU=NIFI'
```

Create keystore, truststore, nifi.properties for 10 NiFi hostnames in each of 4 subdomains:

```
bin/tls-toolkit.sh standalone -n 'nifi[01-10].subdomain[1-4].domain'
```

Create 2 sets of keystore, truststore, nifi.properties for 10 NiFi hostnames in each of 4 subdomains along with a client certificate with the given DN:

```
bin/tls-toolkit.sh standalone -n 'nifi[01-10].subdomain[1-4].domain(2)' -C 'CN=username,OU=NIFI'
```


1.1.2.1.2. Client/Server

Client/Server mode relies on a long-running Certificate Authority (CA) to issue certificates. The CA can be stopped when you're not bringing nodes online.

1.1.2.1.2.1. Server

The CA server is invoked by running `./bin/tls-toolkit.sh server -h` which prints the usage information along with descriptions of options that can be specified.

You can use the following command line options with the `tls-toolkit` in server mode:

- `-a,--keyAlgorithm <arg>` Algorithm to use for generated keys (default: RSA)
- `--configJsonIn <arg>` The place to read configuration info from (defaults to the value of `configJson`), implies `useConfigJson` if set (default: `configJson` value)
- `-d,--days <arg>` Number of days issued certificate should be valid for (default: 1095)
- `-D,--dn <arg>` The dn to use for the CA certificate (default: `CN=YOUR_CA_HOSTNAME,OU=NIFI`)
- `-f,--configJson <arg>` The place to write configuration info (default: `config.json`)
- `-F,--useConfigJson` Flag specifying that all configuration is read from `configJson` to facilitate automated use (otherwise `configJson` will only be written to)
- `-g,--differentKeyAndKeystorePasswords` Use different generated password for the key and the keystore
- `-h,--help` Print help and exit
- `-k,--keySize <arg>` Number of bits for generated keys (default: 2048)
- `-p,--PORT <arg>` The port for the Certificate Authority to listen on (default: 8443)
- `-s,--signingAlgorithm <arg>` Algorithm to use for signing certificates (default: `SHA256WITHRSA`)
- `-T,--keyStoreType <arg>` The type of keystores to generate (default: `jks`)
- `-t,--token <arg>` The token to use to prevent MITM (required and must be same as one used by clients)

1.1.2.1.2.2. Client

The client can be used to request new Certificates from the CA. The client utility generates a keypair and Certificate Signing Request (CSR) and sends the CSR to the Certificate Authority. The client is invoked by running `./bin/tls-toolkit.sh client -h` which prints the usage information along with descriptions of options that can be specified.

You can use the following command line options with the `tls-toolkit` in client mode:

- `-a,--keyAlgorithm <arg>` Algorithm to use for generated keys (default: RSA)
- `-c,--certificateAuthorityHostname <arg>` Hostname of NiFi Certificate Authority (default: `localhost`)

- `-C,--certificateDirectory <arg>` The directory to write the CA certificate (default: .)
- `--configJsonIn <arg>` The place to read configuration info from, implies `useConfigJson` if set (default: configJson value)
- `-D,--dn <arg>` The DN to use for the client certificate (default: CN=<localhost name>, OU=NIFI) (this is auto-populated by the tool)
- `-f,--configJson <arg>` The place to write configuration info (default: config.json)
- `-F,--useConfigJson` Flag specifying that all configuration is read from `configJson` to facilitate automated use (otherwise `configJson` will only be written to)
- `-g,--differentKeyAndKeystorePasswords` Use different generated password for the key and the keystore
- `-h,--help` Print help and exit
- `-k,--keySize <arg>` Number of bits for generated keys (default: 2048)
- `-p,--PORT <arg>` The port to use to communicate with the Certificate Authority (default: 8443)
- `--subjectAlternativeNames <arg>` Comma-separated list of domains to use as Subject Alternative Names in the certificate
- `-T,--keyStoreType <arg>` The type of keystores to generate (default: jks)
- `-t,--token <arg>` The token to use to prevent MITM (required and must be same as one used by CA)

After running the client you will have the CA's certificate, a keystore, a truststore, and a `config.json` with information about them as well as their passwords.

For a client certificate that can be easily imported into the browser, specify: `-T PKCS12`

1.1.3. User Authentication

NiFi supports user authentication via client certificates, via username/password, via Apache Knox, or via OpenId Connect (<http://openid.net/connect>).

Username/password authentication is performed by a 'Login Identity Provider'. The Login Identity Provider is a pluggable mechanism for authenticating users via their username/password. Which Login Identity Provider to use is configured in the `nifi.properties` file. Currently NiFi offers username/password with Login Identity Providers options for LDAP and Kerberos.

The `nifi.login.identity.provider.configuration.file` property specifies the configuration file for Login Identity Providers. The `nifi.security.user.login.identity.provider` property indicates which of the configured Login Identity Provider should be used. By default, this property is not configured meaning that username/password must be explicitly enabled.

During OpenId Connect authentication, NiFi will redirect users to login with the Provider before returning to NiFi. NiFi will then call the Provider to obtain the user identity.

During Apache Knox authentication, NiFi will redirect users to login with Apache Knox before returning to NiFi. NiFi will verify the Apache Knox token during authentication.

NiFi can only be configured for username/password, OpenId Connect, or Apache Knox at a given time. It does not support running each of these concurrently. NiFi will require client certificates for authenticating users over HTTPS if none of these are configured.

A secured instance of NiFi cannot be accessed anonymously unless configured to use an LDAP or Kerberos Login Identity Provider, which in turn must be configured to explicitly allow anonymous access. Anonymous access is not currently possible by the default FileAuthorizer (see [Authorizer Configuration](#)), but is a future effort ([NIFI-2730](#)).

NiFi does not perform user authentication over HTTP. Using HTTP, all users will be granted all roles.

1.1.3.1. Lightweight Directory Access Protocol (LDAP)

Below is an example and description of configuring a Login Identity Provider that integrates with a Directory Server to authenticate users.

```
<provider>
  <identifier>ldap-provider</identifier>
  <class>org.apache.nifi.ldap.LdapProvider</class>
  <property name="Authentication Strategy">START_TLS</property>

  <property name="Manager DN"></property>
  <property name="Manager Password"></property>

  <property name="TLS - Keystore"></property>
  <property name="TLS - Keystore Password"></property>
  <property name="TLS - Keystore Type"></property>
  <property name="TLS - Truststore"></property>
  <property name="TLS - Truststore Password"></property>
  <property name="TLS - Truststore Type"></property>
  <property name="TLS - Client Auth"></property>
  <property name="TLS - Protocol"></property>
  <property name="TLS - Shutdown Gracefully"></property>

  <property name="Referral Strategy">FOLLOW</property>
  <property name="Connect Timeout">10 secs</property>
  <property name="Read Timeout">10 secs</property>

  <property name="Url"></property>
  <property name="User Search Base"></property>
  <property name="User Search Filter"></property>

  <property name="Identity Strategy">USE_DN</property>
  <property name="Authentication Expiration">12 hours</property>
</provider>
```

With this configuration, username/password authentication can be enabled by referencing this provider in *nifi.properties*.

```
nifi.security.user.login.identity.provider=ldap-provider
```

Property Name	Description
Authentication Strategy	How the connection to the LDAP server is authenticated. Possible values are ANONYMOUS, SIMPLE, LDAPS, or START_TLS.
Manager DN	The DN of the manager that is used to bind to the LDAP server to search for users.
Manager Password	The password of the manager that is used to bind to the LDAP server to search for users.
TLS - Keystore	Path to the Keystore that is used when connecting to LDAP using LDAPS or START_TLS.
TLS - Keystore Password	Password for the Keystore that is used when connecting to LDAP using LDAPS or START_TLS.
TLS - Keystore Type	Type of the Keystore that is used when connecting to LDAP using LDAPS or START_TLS (i.e. JKS or PKCS12).
TLS - Truststore	Path to the Truststore that is used when connecting to LDAP using LDAPS or START_TLS.
TLS - Truststore Password	Password for the Truststore that is used when connecting to LDAP using LDAPS or START_TLS.
TLS - Truststore Type	Type of the Truststore that is used when connecting to LDAP using LDAPS or START_TLS (i.e. JKS or PKCS12).
TLS - Client Auth	Client authentication policy when connecting to LDAP using LDAPS or START_TLS. Possible values are REQUIRED, WANT, NONE.
TLS - Protocol	Protocol to use when connecting to LDAP using LDAPS or START_TLS. (i.e. TLS, TLSv1.1, TLSv1.2, etc).
TLS - Shutdown Gracefully	Specifies whether the TLS should be shut down gracefully before the target context is closed. Defaults to false.
Referral Strategy	Strategy for handling referrals. Possible values are FOLLOW, IGNORE, THROW.
Connect Timeout	Duration of connect timeout. (i.e. 10 secs).
Read Timeout	Duration of read timeout. (i.e. 10 secs).
Url	Space-separated list of URLs of the LDAP servers (i.e. ldap://<hostname>:<port>).
User Search Base	Base DN for searching for users (i.e. CN=Users,DC=example,DC=com).
User Search Filter	Filter for searching for users against the 'User Search Base'. (i.e. sAMAccountName={0}). The user specified name is inserted into '{0}'.
Identity Strategy	Strategy to identify users. Possible values are USE_DN and USE_USERNAME. The default functionality if this property is missing is USE_DN in order to retain backward compatibility. USE_DN will use the full DN of the user entry if possible. USE_USERNAME will use the username the user logged in with.
Authentication Expiration	The duration of how long the user authentication is valid for. If the user never logs out, they will be required to log back in following this duration.

1.1.3.2. Kerberos

Below is an example and description of configuring a Login Identity Provider that integrates with a Kerberos Key Distribution Center (KDC) to authenticate users.

```
<provider>
```

```
<identifier>kerberos-provider</identifier>
<class>org.apache.nifi.kerberos.KerberosProvider</class>
<property name="Default Realm">NIFI.APACHE.ORG</property>
<property name="Kerberos Config File">/etc/krb5.conf</property>
<property name="Authentication Expiration">12 hours</property>
</provider>
```

With this configuration, username/password authentication can be enabled by referencing this provider in *nifi.properties*.

```
nifi.security.user.login.identity.provider=kerberos-provider
```

Property Name	Description
Default Realm	Default realm to provide when user enters incomplete user principal (i.e. NIFI.APACHE.ORG).
Kerberos Config File	Absolute path to Kerberos client configuration file.
Authentication Expiration	The duration of how long the user authentication is valid for. If the user never logs out, they will be required to log back in following this duration.

See also [Kerberos Service](#) to allow single sign-on access via client Kerberos tickets.

1.1.3.3. OpenId Connect

To enable authentication via OpenId Connect the following properties must be configured in *nifi.properties*.

Property Name	Description
nifi.security.user.oidc.discovery.url	The discovery URL for the desired OpenId Connect Provider (http://openid.net/specs/openid-connect-discovery-1_0.html).
nifi.security.user.oidc.connect.timeout	Connect timeout when communicating with the OpenId Connect Provider.
nifi.security.user.oidc.read.timeout	Read timeout when communicating with the OpenId Connect Provider.
nifi.security.user.oidc.client.id	The client id for NiFi after registration with the OpenId Connect Provider.
nifi.security.user.oidc.client.secret	The client secret for NiFi after registration with the OpenId Connect Provider.
nifi.security.user.oidc.preferred.jwsalgorithm	The preferred algorithm for validating identity tokens. If this value is blank, it will default to 'RS256' which is required to be supported by the OpenId Connect Provider according to the specification. If this value is 'HS256', 'HS384', or 'HS512', NiFi will attempt to validate HMAC protected tokens using the specified client secret. If this value is 'none', NiFi will attempt to validate unsecured/plain tokens. Other values for this algorithm will attempt to parse as an RSA or EC algorithm to be used in conjunction with the JSON Web Key (JWK) provided through the jwks_uri in the metadata found at the discovery URL.

1.1.3.4. Apache Knox

To enable authentication via Apache Knox the following properties must be configured in *nifi.properties*.

Property Name	Description
<code>nifi.security.user.knox.url</code>	The URL for the Apache Knox log in page.
<code>nifi.security.user.knox.publicKey</code>	The path to the Apache Knox public key that will be used to verify the signatures of the authentication tokens in the HTTP Cookie.
<code>nifi.security.user.knox.cookieName</code>	The name of the HTTP Cookie that Apache Knox will generate after successful log in.
<code>nifi.security.user.knox.audiences</code>	Optional. A comma separate listed of allowed audiences. If set, the audience in the token must be present in this listing. The audience that is populated in the token can be configured in Knox.

1.1.4. Multi-Tenant Authorization

After you have configured NiFi to run securely and with an authentication mechanism, you must configure who has access to the system, and the level of their access. You can do this using 'multi-tenant authorization'. Multi-tenant authorization enables multiple groups of users (tenants) to command, control, and observe different parts of the dataflow, with varying levels of authorization. When an authenticated user attempts to view or modify a NiFi resource, the system checks whether the user has privileges to perform that action. These privileges are defined by policies that you can apply system-wide or to individual components.

1.1.4.1. Authorizer Configuration

An 'authorizer' grants users the privileges to manage users and policies by creating preliminary authorizations at startup.

Authorizers are configured using two properties in the 'nifi.properties' file:

- The `nifi.authorizer.configuration.file` property specifies the configuration file where authorizers are defined. By default, the 'authorizers.xml' file located in the root installation conf directory is selected.
- The `nifi.security.user.authorizer` property indicates which of the configured authorizers in the 'authorizers.xml' file to use.

1.1.4.2. Authorizers.xml Setup

The 'authorizers.xml' file is used to define and configure available authorizers. The default authorizer is the StandardManagedAuthorizer. The managed authorizer is comprised of a UserGroupProvider and a AccessPolicyProvider. The users, group, and access policies will be loaded and optionally configured through these providers. The managed authorizer will make all access decisions based on these provided users, groups, and access policies.

During startup there is a check to ensure that there are no two users/groups with the same identity/name. This check is executed regardless of the configured implementation. This is necessary because this is how users/groups are identified and authorized during access decisions.

The default UserGroupProvider is the FileUserGroupProvider, however, you can develop additional UserGroupProviders as extensions. The FileUserGroupProvider has the following properties:

- Users File - The file where the FileUserGroupProvider stores users and groups. By default, the 'users.xml' in the 'conf' directory is chosen.
- Legacy Authorized Users File - The full path to an existing authorized-users.xml that will be automatically be used to load the users and groups into the Users File.
- Initial User Identity - The identity of a users and systems to seed the Users File. The name of each property must be unique, for example: "Initial User Identity A", "Initial User Identity B", "Initial User Identity C" or "Initial User Identity 1", "Initial User Identity 2", "Initial User Identity 3"

Another option for the UserGroupProvider is the LdapUserGroupProvider. By default, this option is commented out but can be configured in lieu of the FileUserGroupProvider. This will sync users and groups from a directory server and will present them in NiFi UI in read only form. The LdapUserGroupProvider has the following properties:

- Authentication Strategy - How the connection to the LDAP server is authenticated. Possible values are ANONYMOUS, SIMPLE, LDAPS, or START_TLS
- Manager DN - The DN of the manager that is used to bind to the LDAP server to search for users.
- Manager Password - The password of the manager that is used to bind to the LDAP server to search for users.
- TLS - Keystore - Path to the Keystore that is used when connecting to LDAP using LDAPS or START_TLS.
- TLS - Keystore Password - Password for the Keystore that is used when connecting to LDAP using LDAPS or START_TLS.
- TLS - Keystore Type - Type of the Keystore that is used when connecting to LDAP using LDAPS or START_TLS (i.e. JKS or PKCS12).
- TLS - Truststore - Path to the Truststore that is used when connecting to LDAP using LDAPS or START_TLS.
- TLS - Truststore Password - Password for the Truststore that is used when connecting to LDAP using LDAPS or START_TLS.
- TLS - Truststore Type - Type of the Truststore that is used when connecting to LDAP using LDAPS or START_TLS (i.e. JKS or PKCS12).
- TLS - Client Auth - Client authentication policy when connecting to LDAP using LDAPS or START_TLS. Possible values are REQUIRED, WANT, NONE.
- TLS - Protocol - Protocol to use when connecting to LDAP using LDAPS or START_TLS. (i.e. TLS, TLSv1.1, TLSv1.2, etc).
- TLS - Shutdown Gracefully - Specifies whether the TLS should be shut down gracefully before the target context is closed. Defaults to false.
- Referral Strategy - Strategy for handling referrals. Possible values are FOLLOW, IGNORE, THROW.

- Connect Timeout - Duration of connect timeout. (i.e. 10 secs).
- Read Timeout - Duration of read timeout. (i.e. 10 secs).
- Url - Space-separated list of URLs of the LDAP servers (i.e. ldap://<hostname>:<port>).
- Page Size - Sets the page size when retrieving users and groups. If not specified, no paging is performed.
- Sync Interval - Duration of time between syncing users and groups. (i.e. 30 mins). Minimum allowable value is 10 secs.
- User Search Base - Base DN for searching for users (i.e. ou=users,o=nifi). Required to search users.
- User Object Class - Object class for identifying users (i.e. person). Required if searching users.
- User Search Scope - Search scope for searching users (ONE_LEVEL, OBJECT, or SUBTREE). Required if searching users.
- User Search Filter - Filter for searching for users against the 'User Search Base' (i.e. (memberof=cn=team1,ou=groups,o=nifi)). Optional.
- User Identity Attribute - Attribute to use to extract user identity (i.e. cn). Optional. If not set, the entire DN is used.
- User Group Name Attribute - Attribute to use to define group membership (i.e. memberof). Optional. If not set group membership will not be calculated through the users. Will rely on group membership being defined through 'Group Member Attribute' if set. The value of this property is the name of the attribute in the user ldap entry that associates them with a group. The value of that user attribute could be a dn or group name for instance. What value is expected is configured in the 'User Group Name Attribute - Referenced Group Attribute'.
- User Group Name Attribute - Referenced Group Attribute - If blank, the value of the attribute defined in 'User Group Name Attribute' is expected to be the full dn of the group. If not blank, this property will define the attribute of the group ldap entry that the value of the attribute defined in 'User Group Name Attribute' is referencing (i.e. name). Use of this property requires that 'Group Search Base' is also configured.
- Group Search Base - Base DN for searching for groups (i.e. ou=groups,o=nifi). Required to search groups.
- Group Object Class - Object class for identifying groups (i.e. groupOfNames). Required if searching groups.
- Group Search Scope - Search scope for searching groups (ONE_LEVEL, OBJECT, or SUBTREE). Required if searching groups.
- Group Search Filter - Filter for searching for groups against the 'Group Search Base'. Optional.
- Group Name Attribute - Attribute to use to extract group name (i.e. cn). Optional. If not set, the entire DN is used.

- Group Member Attribute - Attribute to use to define group membership (i.e. member). Optional. If not set group membership will not be calculated through the groups. Will rely on group membership being defined through 'User Group Name Attribute' if set. The value of this property is the name of the attribute in the group ldap entry that associates them with a user. The value of that group attribute could be a dn or memberId for instance. What value is expected is configured in the 'Group Member Attribute - Referenced User Attribute'. (i.e. member: cn=User 1,ou=users,o=nifi vs. memberId: user1)
- Group Member Attribute - Referenced User Attribute - If blank, the value of the attribute defined in 'Group Member Attribute' is expected to be the full dn of the user. If not blank, this property will define the attribute of the user ldap entry that the value of the attribute defined in 'Group Member Attribute' is referencing (i.e. uid). Use of this property requires that 'User Search Base' is also configured. (i.e. member: cn=User 1,ou=users,o=nifi vs. memberId: user1)

Another option for the UserGroupProvider are composite implementations. This means that multiple sources/implementations can be configured and composed. For instance, an admin can configure users/groups to be loaded from a file and a directory server. There are two composite implementations, one that supports multiple UserGroupProviders and one that supports multiple UserGroupProviders and a single configurable UserGroupProvider.

The CompositeUserGroupProvider will provide support for retrieving users and groups from multiple sources. The CompositeUserGroupProvider has the following properties:

- User Group Provider - The identifier of user group providers to load from. The name of each property must be unique, for example: "User Group Provider A", "User Group Provider B", "User Group Provider C" or "User Group Provider 1", "User Group Provider 2", "User Group Provider 3"

The CompositeConfigurableUserGroupProvider will provide support for retrieving users and groups from multiple sources. Additionally, a single configurable user group provider is required. Users from the configurable user group provider are configurable, however users loaded from one of the User Group Provider [unique key] will not be. The CompositeConfigurableUserGroupProvider has the following properties:

- Configurable User Group Provider - A configurable user group provider.
- User Group Provider - The identifier of user group providers to load from. The name of each property must be unique, for example: "User Group Provider A", "User Group Provider B", "User Group Provider C" or "User Group Provider 1", "User Group Provider 2", "User Group Provider 3"

The default AccessPolicyProvider is the FileAccessPolicyProvider, however, you can develop additional AccessPolicyProvider as extensions. The FileAccessPolicyProvider has the following properties:

- User Group Provider - The identifier for an User Group Provider defined above that will be used to access users and groups for use in the managed access policies.
- Authorizations File - The file where the FileAccessPolicyProvider will store policies.
- Initial Admin Identity - The identity of an initial admin user that will be granted access to the UI and given the ability to create additional users, groups, and policies. The value

of this property could be a DN when using certificates or LDAP, or a Kerberos principal. This property will only be used when there are no other policies defined. If this property is specified then a Legacy Authorized Users File can not be specified.

- Legacy Authorized Users File - The full path to an existing authorized-users.xml that will be automatically converted to the new authorizations model. If this property is specified then an Initial Admin Identity can not be specified, and this property will only be used when there are no other users, groups, and policies defined.
- Node Identity - The identity of a NiFi cluster node. When clustered, a property for each node should be defined, so that every node knows about every other node. If not clustered these properties can be ignored. The name of each property must be unique, for example for a three node cluster: "Node Identity A", "Node Identity B", "Node Identity C" or "Node Identity 1", "Node Identity 2", "Node Identity 3"

The identities configured in the Initial Admin Identity, the Node Identity properties, or discovered in a Legacy Authorized Users File must be available in the configured User Group Provider.

The default authorizer is the StandardManagedAuthorizer, however, you can develop additional authorizers as extensions. The StandardManagedAuthorizer has the following properties:

- Access Policy Provider - The identifier for an Access Policy Provider defined above.

The FileAuthorizer has been replaced with the more granular StandardManagedAuthorizer approach described above. However, it is still available for backwards compatibility reasons. The FileAuthorizer has the following properties.

- Authorizations File - The file where the FileAuthorizer stores policies. By default, the 'authorizations.xml' in the 'conf' directory is chosen.
- Users File - The file where the FileAuthorizer stores users and groups. By default, the 'users.xml' in the 'conf' directory is chosen.
- Initial Admin Identity - The identity of an initial admin user that is granted access to the UI and given the ability to create additional users, groups, and policies. This property is only used when there are no other users, groups, and policies defined.
- Legacy Authorized Users File - The full path to an existing authorized-users.xml that is automatically converted to the multi-tenant authorization model. This property is only used when there are no other users, groups, and policies defined.
- Node Identity - The identity of a NiFi cluster node. When clustered, a property for each node should be defined, so that every node knows about every other node. If not clustered, these properties can be ignored.

1.1.4.2.1. Initial Admin Identity (New NiFi Instance)

If you are setting up a secured NiFi instance for the first time, you must manually designate an "Initial Admin Identity" in the 'authorizers.xml' file. This initial admin user is granted access to the UI and given the ability to create additional users, groups, and policies. The value of this property could be a DN (when using certificates or LDAP) or a Kerberos principal. If you are the NiFi administrator, add yourself as the "Initial Admin Identity".

Here is an example LDAP entry using the name John Smith:

```
<authorizers>
  <userGroupProvider>
    <identifier>file-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.FileUserGroupProvider</class>
    <property name="Users File">./conf/users.xml</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Initial User Identity 1">cn=John Smith,ou=people,dc=
example,dc=com</property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">file-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">cn=John Smith,ou=people,dc=
example,dc=com</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1"></property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>
```

Here is an example Kerberos entry using the name John Smith and realm NIFI.APACHE.ORG:

```
<authorizers>
  <userGroupProvider>
    <identifier>file-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.FileUserGroupProvider</class>
    <property name="Users File">./conf/users.xml</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Initial User Identity 1">johnsmith@NIFI.APACHE.ORG</
property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">file-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">johnsmith@NIFI.APACHE.ORG</
property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1"></property>
  </accessPolicyProvider>
  <authorizer>
```

```

    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>

```

After you have edited and saved the 'authorizers.xml' file, restart NiFi. The "Initial Admin Identity" user and administrative policies are added to the 'users.xml' and 'authorizations.xml' files during restart. Once NiFi starts, the "Initial Admin Identity" user is able to access the UI and begin managing users, groups, and policies.

For a brand new secure flow, providing the "Initial Admin Identity" gives that user access to get into the UI and to manage users, groups and policies. But if that user wants to start modifying the flow, they need to grant themselves policies for the root process group. The system is unable to do this automatically because in a new flow the UUID of the root process group is not permanent until the flow.xml.gz is generated. If the NiFi instance is an upgrade from an existing flow.xml.gz or a 1.x instance going from unsecure to secure, then the "Initial Admin Identity" user is automatically given the privileges to modify the flow.

Here is an example loading users and groups from LDAP. Group membership will be driven through the member attribute of each group. Authorization will still use file based access policies:

```

dn: cn=User 1,ou=users,o=nifi
objectClass: organizationalPerson
objectClass: person
objectClass: inetOrgPerson
objectClass: top
cn: User 1
sn: User1
uid: user1

dn: cn=User 2,ou=users,o=nifi
objectClass: organizationalPerson
objectClass: person
objectClass: inetOrgPerson
objectClass: top
cn: User 2
sn: User2
uid: user2

dn: cn=admins,ou=groups,o=nifi
objectClass: groupOfNames
objectClass: top
cn: admins
member: cn=User 1,ou=users,o=nifi
member: cn=User 2,ou=users,o=nifi

<authorizers>
  <userGroupProvider>
    <identifier>ldap-user-group-provider</identifier>
    <class>org.apache.nifi.ldap.tenants.LdapUserGroupProvider</class>
    <property name="Authentication Strategy">ANONYMOUS</property>

    <property name="Manager DN"></property>
  </userGroupProvider>
</authorizers>

```

```

    <property name="Manager Password"></property>

    <property name="TLS - Keystore"></property>
    <property name="TLS - Keystore Password"></property>
    <property name="TLS - Keystore Type"></property>
    <property name="TLS - Truststore"></property>
    <property name="TLS - Truststore Password"></property>
    <property name="TLS - Truststore Type"></property>
    <property name="TLS - Client Auth"></property>
    <property name="TLS - Protocol"></property>
    <property name="TLS - Shutdown Gracefully"></property>

    <property name="Referral Strategy">FOLLOW</property>
    <property name="Connect Timeout">10 secs</property>
    <property name="Read Timeout">10 secs</property>

    <property name="Url">ldap://localhost:10389</property>
    <property name="Page Size"></property>
    <property name="Sync Interval">30 mins</property>

    <property name="User Search Base">ou=users,o=nifi</property>
    <property name="User Object Class">person</property>
    <property name="User Search Scope">ONE_LEVEL</property>
    <property name="User Search Filter"></property>
    <property name="User Identity Attribute">cn</property>
    <property name="User Group Name Attribute"></property>
    <property name="User Group Name Attribute - Referenced Group
Attribute"></property>

    <property name="Group Search Base">ou=groups,o=nifi</property>
    <property name="Group Object Class">groupOfNames</property>
    <property name="Group Search Scope">ONE_LEVEL</property>
    <property name="Group Search Filter"></property>
    <property name="Group Name Attribute">cn</property>
    <property name="Group Member Attribute">member</property>
    <property name="Group Member Attribute - Referenced User Attribute"></
property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">ldap-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">John Smith</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1"></property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>

```

The 'Initial Admin Identity' value would have loaded from the cn from John Smith's entry based on the 'User Identity Attribute' value.

Here is an example loading users and groups from LDAP. Group membership will be driven through the member attribute of each group. Authorization will still use file based access policies:

```
dn: uid=User 1,ou=Users,dc=local
objectClass: inetOrgPerson
objectClass: posixAccount
objectClass: shadowAccount
uid: user1
cn: User 1

dn: uid=User 2,ou=Users,dc=local
objectClass: inetOrgPerson
objectClass: posixAccount
objectClass: shadowAccount
uid: user2
cn: User 2

dn: cn=Managers,ou=Groups,dc=local
objectClass: posixGroup
cn: Managers
memberUid: user1
memberUid: user2

<authorizers>
  <userGroupProvider>
    <identifier>ldap-user-group-provider</identifier>
    <class>org.apache.nifi.ldap.tenants.LdapUserGroupProvider</class>
    <property name="Authentication Strategy">ANONYMOUS</property>

    <property name="Manager DN"></property>
    <property name="Manager Password"></property>

    <property name="TLS - Keystore"></property>
    <property name="TLS - Keystore Password"></property>
    <property name="TLS - Keystore Type"></property>
    <property name="TLS - Truststore"></property>
    <property name="TLS - Truststore Password"></property>
    <property name="TLS - Truststore Type"></property>
    <property name="TLS - Client Auth"></property>
    <property name="TLS - Protocol"></property>
    <property name="TLS - Shutdown Gracefully"></property>

    <property name="Referral Strategy">FOLLOW</property>
    <property name="Connect Timeout">10 secs</property>
    <property name="Read Timeout">10 secs</property>

    <property name="Url">ldap://localhost:10389</property>
    <property name="Page Size"></property>
    <property name="Sync Interval">30 mins</property>

    <property name="User Search Base">ou=Groups,dc=local</property>
    <property name="User Object Class">posixAccount</property>
    <property name="User Search Scope">ONE_LEVEL</property>
    <property name="User Search Filter"></property>
    <property name="User Identity Attribute">cn</property>
    <property name="User Group Name Attribute"></property>
    <property name="User Group Name Attribute - Referenced Group
Attribute"></property>
```

```

    <property name="Group Search Base">ou=Groups,dc=local</property>
    <property name="Group Object Class">posixGroup</property>
    <property name="Group Search Scope">ONE_LEVEL</property>
    <property name="Group Search Filter"></property>
    <property name="Group Name Attribute">cn</property>
    <property name="Group Member Attribute">memberUid</property>
    <property name="Group Member Attribute - Referenced User
Attribute">uid</property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">ldap-user-group-provider</
property>
  <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">John Smith</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1"></property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>

```

Here is an example composite implementation loading users and groups from LDAP and a local file. Group membership will be driven through the member attribute of each group. The users from LDAP will be read only while the users loaded from the file will be configurable in UI.

```

<authorizers>
  <userGroupProvider>
    <identifier>file-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.FileUserGroupProvider</class>
    <property name="Users File">./conf/users.xml</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Initial User Identity 1">cn=nifi-nodel,ou=servers,dc=
example,dc=com</property>
    <property name="Initial User Identity 2">cn=nifi-node2,ou=servers,dc=
example,dc=com</property>
  </userGroupProvider>
  <userGroupProvider>
    <identifier>ldap-user-group-provider</identifier>
    <class>org.apache.nifi.ldap.tenants.LdapUserGroupProvider</class>
    <property name="Authentication Strategy">ANONYMOUS</property>

    <property name="Manager DN"></property>
    <property name="Manager Password"></property>

    <property name="TLS - Keystore"></property>
    <property name="TLS - Keystore Password"></property>
    <property name="TLS - Keystore Type"></property>
    <property name="TLS - Truststore"></property>
    <property name="TLS - Truststore Password"></property>
    <property name="TLS - Truststore Type"></property>

```

```

<property name="TLS - Client Auth"></property>
<property name="TLS - Protocol"></property>
<property name="TLS - Shutdown Gracefully"></property>

<property name="Referral Strategy">FOLLOW</property>
<property name="Connect Timeout">10 secs</property>
<property name="Read Timeout">10 secs</property>

<property name="Url">ldap://localhost:10389</property>
<property name="Page Size"></property>
<property name="Sync Interval">30 mins</property>

<property name="User Search Base">ou=users,o=nifi</property>
<property name="User Object Class">person</property>
<property name="User Search Scope">ONE_LEVEL</property>
<property name="User Search Filter"></property>
<property name="User Identity Attribute">cn</property>
<property name="User Group Name Attribute"></property>
<property name="User Group Name Attribute - Referenced Group
Attribute"></property>

<property name="Group Search Base">ou=groups,o=nifi</property>
<property name="Group Object Class">groupOfNames</property>
<property name="Group Search Scope">ONE_LEVEL</property>
<property name="Group Search Filter"></property>
<property name="Group Name Attribute">cn</property>
<property name="Group Member Attribute">member</property>
<property name="Group Member Attribute - Referenced User Attribute"></
property>
  </userGroupProvider>
  <userGroupProvider>
    <identifier>composite-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.
CompositeConfigurableUserGroupProvider</class>
    <property name="Configurable User Group Provider">file-user-group-
provider</property>
    <property name="User Group Provider 1">ldap-user-group-provider</
property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">composite-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">John Smith</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1">cn=nifi-node1,ou=servers,dc=example,
dc=com</property>
    <property name="Node Identity 2">cn=nifi-node2,ou=servers,dc=example,
dc=com</property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>

```



```
</authorizers>
```

In this example, the users and groups are loaded from LDAP but the servers are managed in a local file. The 'Initial Admin Identity' value came from an attribute in a LDAP entry based on the 'User Identity Attribute'. The 'Node Identity' values are established in the local file using the 'Initial User Identity' properties.

1.1.4.2.2. Legacy Authorized Users (NiFi Instance Upgrade)

If you are upgrading from a 0.x NiFi instance, you can convert your previously configured users and roles to the multi-tenant authorization model. In the 'authorizers.xml' file, specify the location of your existing 'authorized-users.xml' file in the "Legacy Authorized Users File" property.

Here is an example entry:

```
<authorizers>
  <userGroupProvider>
    <identifier>file-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.FileUserGroupProvider</class>
    <property name="Users File">./conf/users.xml</property>
    <property name="Legacy Authorized Users File">/Users/johnsmith/
config_files/authorized-users.xml</property>

    <property name="Initial User Identity 1"></property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">file-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity"></property>
    <property name="Legacy Authorized Users File">/Users/johnsmith/
config_files/authorized-users.xml</property>

    <property name="Node Identity 1"></property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>
```

After you have edited and saved the 'authorizers.xml' file, restart NiFi. Users and roles from the 'authorized-users.xml' file are converted and added as identities and policies in the 'users.xml' and 'authorizations.xml' files. Once the application starts, users who previously had a legacy Administrator role can access the UI and begin managing users, groups, and policies.

The following tables summarize the global and component policies assigned to each legacy role if the NiFi instance has an existing 'flow.xml.gz':

1.1.4.2.2.1. Global Access Policies

	Admin	DFM	Monitor	Provenance	NiFi	Proxy
view the UI	*	*	*			
access the controller - view	*	*	*		*	
access the controller - modify		*				
query provenance				*		
access restricted components		*				
access all policies - view	*					
access all policies - modify	*					
access users/ user groups - view	*					
access users/ user groups - modify	*					
retrieve site-to-site details					*	
view system diagnostics		*	*			
proxy user requests						*
access counters						

1.1.4.2.2.2. Component Access Policies on the Root Process Group

	Admin	DFM	Monitor	Provenance	NiFi	Proxy
view the component	*	*	*			
modify the component		*				
view the data		*		*		*
modify the data		*				*

For details on the individual policies in the table, see [Access Policies](#).

NiFi fails to restart if values exist for both the "Initial Admin Identity" and "Legacy Authorized Users File" properties. You can specify only one of these values to initialize authorizations.

Do not manually edit the 'authorizations.xml' file. Create authorizations only during initial setup and afterwards using the NiFi UI.

1.1.4.2.3. Cluster Node Identities

If you are running NiFi in a clustered environment, you must specify the identities for each node. The authorization policies required for the nodes to communicate are created during startup.

For example, if you are setting up a 2 node cluster with the following DNs for each node:

```
cn=nifi-1,ou=people,dc=example,dc=com
cn=nifi-2,ou=people,dc=example,dc=com
```

```
<authorizers>
  <userGroupProvider>
    <identifier>file-user-group-provider</identifier>
    <class>org.apache.nifi.authorization.FileUserGroupProvider</class>
    <property name="Users File">./conf/users.xml</property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Initial User Identity 1">johnsmith@NIFI.APACHE.ORG</
property>
    <property name="Initial User Identity 2">cn=nifi-1,ou=people,dc=
example,dc=com</property>
    <property name="Initial User Identity 3">cn=nifi-2,ou=people,dc=
example,dc=com</property>
  </userGroupProvider>
  <accessPolicyProvider>
    <identifier>file-access-policy-provider</identifier>
    <class>org.apache.nifi.authorization.FileAccessPolicyProvider</class>
    <property name="User Group Provider">file-user-group-provider</
property>
    <property name="Authorizations File">./conf/authorizations.xml</
property>
    <property name="Initial Admin Identity">johnsmith@NIFI.APACHE.ORG</
property>
    <property name="Legacy Authorized Users File"></property>

    <property name="Node Identity 1">cn=nifi-1,ou=people,dc=example,dc=
com</property>
    <property name="Node Identity 2">cn=nifi-2,ou=people,dc=example,dc=
com</property>
  </accessPolicyProvider>
  <authorizer>
    <identifier>managed-authorizer</identifier>
    <class>org.apache.nifi.authorization.StandardManagedAuthorizer</class>
    <property name="Access Policy Provider">file-access-policy-provider</
property>
  </authorizer>
</authorizers>
```

In a cluster, all nodes must have the same 'authorizations.xml' and 'users.xml'. The only exception is if a node has empty 'authorizations.xml' and 'user.xml' files prior to joining the cluster. In this scenario, the node inherits them from the cluster during startup.

Now that initial authorizations have been created, additional users, groups and authorizations can be created and managed in the NiFi UI.

1.1.4.3. Configuring Users & Access Policies

Depending on the capabilities of the configured `UserGroupProvider` and `AccessPolicyProvider` the users, groups, and policies will be configurable in the UI. If the extensions are not configurable the users, groups, and policies will read-only in the UI. If the configured authorizer does not use `UserGroupProvider` and `AccessPolicyProvider` the users and policies may or may not be visible and configurable in the UI based on the underlying implementation.


This section assumes the users, groups, and policies are configurable in the UI and describes:

- How to create users and groups
- How access policies are used to define authorizations
- How to view policies that are set on a user
- How to configure access policies by walking through specific examples

Instructions requiring interaction with the UI assume the application is being accessed by `User1`, a user with administrator privileges, such as the "Initial Admin Identity" user or a converted legacy admin user (see [Authorizers.xml Setup](#)).

1.1.4.3.1. Creating Users and Groups

From the UI, select "Users" from the Global Menu. This opens a dialog to create and manage users and groups.




Click the Add icon



(

).

To create a user, enter the 'Identity' information relevant to the authentication method chosen to secure your NiFi instance. Click OK.



The image shows a dialog box titled "User/Group". At the top, there is a dark blue header with the text "User/Group" in white. Below the header, there are two radio buttons: "Individual" (which is selected, indicated by a blue dot) and "Group" (which is unselected, indicated by an empty circle). Below the radio buttons, there is a text input field labeled "Identity" containing the text "User2". Below the input field, there is a label "Member of" followed by a large empty space. At the bottom right of the dialog box, there are two buttons: "CANCEL" and "OK".

To create a group, select the "Group" radio button, enter the name of the group and select the users to be included in the group. Click OK.

1.1.4.3.2. Access Policies

You can manage the ability for users and groups to view or modify NiFi resources using 'access policies'. There are two types of access policies that can be applied to a resource:

- View - If a view policy is created for a resource, only the users or groups that are added to that policy are able to see the details of that resource.
- Modify - If a resource has a modify policy, only the users or groups that are added to that policy can change the configuration of that resource.

You can create and apply access policies on both global and component levels.

1.1.4.3.2.1. Global Access Policies

Global access policies govern the following system level authorizations:

Policy	Privilege	Global Menu Selection
view the UI	Allow users to view the UI	N/A

Policy	Privilege	Global Menu Selection
access the controller	Allows users to view/modify the controller including Reporting Tasks, Controller Services, and Nodes in the Cluster	Controller Settings
query provenance	Allows users to submit a Provenance Search and request Event Lineage	Data Provenance
access restricted components	Allows users to create/modify restricted components assuming otherwise sufficient permissions	N/A
access all policies	Allows users to view/modify the policies for all components	Policies
access users/user groups	Allows users to view/modify the users and user groups	Users
retrieve site-to-site details	Allows other NiFi instances to retrieve Site-To-Site details	N/A
view system diagnostics	Allows users to view System Diagnostics	Summary
proxy user requests	Allows proxy machines to send requests on the behalf of others	N/A
access counters	Allows users to view/modify Counters	Counters

1.1.4.3.2.2. Component Level Access Policies

Component level access policies govern the following component level authorizations:

Policy	Privilege
view the component	Allows users to view component configuration details
modify the component	Allows users to modify component configuration details
view the data	Allows user to view metadata and content for this component through provenance data and flowfile queues in outbound connections
modify the data	Allows user to empty flowfile queues in outbound connections and submit replays
view the policies	Allows users to view the list of users who can view/modify a component
modify the policies	Allows users to modify the list of users who can view/modify a component
receive data via site-to-site	Allows a port to receive data from NiFi instances
send data via site-to-site	Allows a port to send data from NiFi instances

You can apply access policies to all component types except connections. Connection authorizations are inferred by the individual access policies on the source and destination components of the connection, as well as the access policy of the process group containing the components. This is discussed in more detail in the [Creating a Connection](#) and [Editing a Connection](#) examples below.

In order to access List Queue or Delete Queue for a connection, a user requires permission to the "view the data" and "modify the data" policies on the component. In a clustered environment, all nodes must be added to these policies as well, as a user request could be replicated through any node in the cluster.

1.1.4.3.2.3. Access Policy Inheritance

An administrator does not need to manually create policies for every component in the dataflow. To reduce the amount of time admins spend on authorization management, policies are inherited from parent resource to child resource. For example, if a user is given access to view and modify a process group, that user can also view and modify the components in the process group. Policy inheritance enables an administrator to assign policies at one time and have the policies apply throughout the entire dataflow.


You can override an inherited policy (as described in the [Moving a Processor](#) example below). Overriding a policy removes the inherited policy, breaking the chain of inheritance from parent to child, and creates a replacement policy to add users as desired. Inherited policies and their users can be restored by deleting the replacement policy.

"View the policies" and "modify the policies" component-level access policies are an exception to this inherited behavior. When a user is added to either policy, they are added to the current list of administrators. They do not override higher level administrators. For this reason, only component specific administrators are displayed for the "view the policies" and "modify the policies" access policies.

You cannot modify the users/groups on an inherited policy. Users and groups can only be added or removed from a parent policy or an override policy.

1.1.4.3.3. Viewing Policies on Users


From the UI, select "Users" from the Global Menu. This opens the NiFi Users dialog.



Select the View User Policies icon



).



The User Policies window displays the global and component level policies that have been set for the chosen user. Select the Go To icon




to navigate to that component in the canvas.


1.1.4.3.4. Access Policy Configuration Examples

The most effective way to understand how to create and apply access policies is to walk through some common examples. The following scenarios assume User1 is an administrator and User2 is a newly added user that has only been given access to the UI.

Let's begin with two processors on the canvas as our starting point: GenerateFlowFile and LogAttribute.




User1 can add components to the dataflow and is able to move, edit and connect all processors. The details and properties of the root process group and processors are visible to User1.



User1 wants to maintain their current privileges to the dataflow and its components.

User2 is unable to add components to the dataflow or move, edit, or connect components. The details and properties of the root process group and processors are hidden from User2.



1.1.4.3.4.1. Moving a Processor


To allow User2 to move the GenerateFlowFile processor in the dataflow and only that processor, User1 performs the following steps:

1. Select the GenerateFlowFile processor so that it is highlighted.
2. Select the Access Policies icon




from the Operate palette and the Access Policies dialog opens.

3. Select "modify the component" from the policy drop-down. The "modify the component" policy that currently exists on the processor (child) is the "modify the component" policy inherited from the root process group (parent) on which User1 has privileges.





4. Select the Override link in the policy inheritance message. When creating the replacement policy, you are given a choice to override with a copy of the inherited policy or an empty policy. Select the Override button to create a copy.



5. On the replacement policy that is created, select the Add User icon



(Find or enter User2 in the User Identity field and select OK. With these changes, User1 maintains the ability to move both processors on the canvas. User2 can now move the GenerateFlowFile processor but cannot move the LogAttribute processor.)



1.1.4.3.4.2. Editing a Processor

In the "Moving a Processor" example above, User2 was added to the "modify the component" policy for GenerateFlowFile. Without the ability to view the processor properties, User2 is unable to modify the processor's configuration. In order to edit a component, a user must be on both the "view the component" and "modify the component" policies. To implement this, User1 performs the following steps:


1. Select the GenerateFlowFile processor.

2. Select the Access Policies icon



from the Operate palette and the Access Policies dialog opens.



3. Select "view the component" from the policy drop-down. The view the component" policy that currently exists on the processor (child) is the "view the component" policy inherited from the root process group (parent) on which User1 has privileges.



4. Select the Override link in the policy inheritance message, keep the default of Copy policy and select the Override button.
5. On the override policy that is created, select the Add User icon




Find or enter User2 in the User Identity field and select OK. With these changes, User1 maintains the ability to view and edit the processors on the canvas. User2 can now view and edit the GenerateFlowFile processor.




1.1.4.3.4.3. Creating a Connection

With the access policies configured as discussed in the previous two examples, User1 is able to connect GenerateFlowFile to LogAttribute:



User2 cannot make the connection:



This is because:

- User2 does not have modify access on the process group.
- Even though User2 has view and modify access to the source component (GenerateFlowFile), User2 does not have an access policy on the destination component (LogAttribute).

To allow User2 to connect GenerateFlowFile to LogAttribute, as User1:


1. Select the root process group. The Operate palette is updated with details for the root process group.

- 2. Select the Access Policies icon



from the Operate palette and the Access Policies dialog opens.


- 3. Select "modify the component" from the policy drop-down.



- 4. Select the Add User icon




Find or enter User2 and select OK.




By adding User2 to the "modify the component" policy on the process group, User2 is added to the "modify the component" policy on


the LogAttribute processor by policy inheritance. To confirm this, highlight the LogAttribute processor and select the Access Policies icon

()
from the Operate palette:




With these changes, User2 can now connect the GenerateFlowFile processor to the LogAttribute processor.






1.1.4.3.4.4. Editing a Connection


Assume User1 or User2 adds a ReplaceText processor to the root process group:



User1 can select and change the existing connection (between GenerateFlowFile to LogAttribute) to now connect GenerateFlowFile to ReplaceText:



User 2 is unable to perform this action.



To allow User2 to connect GenerateFlowFile to ReplaceText, as User1:


1. Select the root process group. The Operate palette is updated with details for the root process group.

2. Select the Access Policies icon



).


3. Select "view the component" from the policy drop-down.




4. Select the Add User icon



Find or enter User2 and select OK.



Being added to both the view and modify policies for the process group, User2 can now connect the GenerateFlowFile processor to the ReplaceText processor.



1.1.5. Encryption Configuration

This section provides an overview of the capabilities of NiFi to encrypt and decrypt data.

The `EncryptContent` processor allows for the encryption and decryption of data, both internal to NiFi and integrated with external systems, such as `openssl` and other data sources and consumers.

1.1.5.1. Key Derivation Functions

Key Derivation Functions (KDF) are mechanisms by which human-readable information, usually a password or other secret information, is translated into a cryptographic key suitable for data protection. For further information, read [the Wikipedia entry on Key Derivation Functions](#). Currently, KDFs are ingested by `CipherProvider` implementations and return a fully-initialized `Cipher` object to be used for encryption or decryption. Due to the use of a `CipherProviderFactory`, the KDFs are not customizable at this time. Future enhancements will include the ability to provide custom cost parameters to the KDF at initialization time. As a work-around, `CipherProvider` instances can be initialized with custom cost parameters in the constructor but this is not currently supported by the `CipherProviderFactory`. Here are the KDFs currently supported by NiFi (primarily in the `EncryptContent` processor for password-based encryption (PBE)) and relevant notes:

- NiFi Legacy KDF
 - The original KDF used by NiFi for internal key derivation for PBE, this is 1000 iterations of the MD5 digest over the concatenation of the password and 8 or 16 bytes of random salt (the salt length depends on the selected cipher block size).
 - This KDF is **deprecated as of NiFi 0.5.0** and should only be used for backwards compatibility to decrypt data that was previously encrypted by a legacy version of NiFi.
- OpenSSL PKCS#5 v1.5 `EVP_BytesToKey`

- This KDF was added in v0.4.0.
- This KDF is provided for compatibility with data encrypted using OpenSSL's default PBE, known as `EVP_BytesToKey`. This is a single iteration of MD5 over the concatenation of the password and 8 bytes of random ASCII salt. OpenSSL recommends using `PBKDF2` for key derivation but does not expose the library method necessary to the command-line tool, so this KDF is still the de facto default for command-line encryption.
- Bcrypt
 - This KDF was added in v0.5.0.
 - Bcrypt is an adaptive function based on the Blowfish cipher. This KDF is strongly recommended as it automatically incorporates a random 16 byte salt, configurable cost parameter (or "work factor"), and is hardened against brute-force attacks using GPGPU (which share memory between cores) by requiring access to "large" blocks of memory during the key derivation. It is less resistant to FPGA brute-force attacks where the gate arrays have access to individual embedded RAM blocks.
 - Because the length of a Bcrypt-derived key is always 184 bits, the complete output is then fed to a SHA-512 digest and truncated to the desired key length. This provides the benefit of the avalanche effect on the formatted input.
 - The recommended minimum work factor is 12 (2^{12} key derivation rounds) (as of 2/1/2016 on commodity hardware) and should be increased to the threshold at which legitimate systems will encounter detrimental delays (see schedule below or use `BcryptCipherProviderGroovyTest#testDefaultConstructorShouldProvideStrongWorkFactor` to calculate safe minimums).
 - The salt format is `$2a$10$ABCDEFGHIJKLMNQRSTUUV`. The salt is delimited by `$` and the three sections are as follows:
 - `2a` - the version of the format. An extensive explanation can be found [here](#). NiFi currently uses `2a` for all salts generated internally.
 - `10` - the work factor. This is actually the \log_2 value, so the total iteration count would be 2^{10} in this case.
 - `ABCDEFGHIJKLMNQRSTUUV` - the 22 character, Base64-encoded, unpadding, raw salt value. This decodes to a 16 byte salt used in the key derivation.
- Scrypt
 - This KDF was added in v0.5.0.
 - Scrypt is an adaptive function designed in response to `bcrypt`. This KDF is recommended as it requires relatively large amounts of memory for each derivation, making it resistant to hardware brute-force attacks.
 - The recommended minimum cost is $N=2^{14}$, $r=8$, $p=1$ (as of 2/1/2016 on commodity hardware) and should be increased to the threshold at which legitimate systems will encounter detrimental delays (see schedule below or use

`ScriptCipherProviderGroovyTest#testDefaultConstructorShouldProvideStrongPar`
to calculate safe minimums).

- The salt format is `$s0$e0101$ABCDEFGHIJKLMN0PQRSTUVWXYZ`. The salt is delimited by `$` and the three sections are as follows:
 - `s0` - the version of the format. NiFi currently uses `s0` for all salts generated internally.
 - `e0101` - the cost parameters. This is actually a hexadecimal encoding of `N`, `r`, `p` using shifts. This can be formed/parsed using `Script#encodeParams()` and `Script#parseParameters()`.
 - Some external libraries encode `N`, `r`, and `p` separately in the form `$400$1$1$`. A utility method is available at `ScriptCipherProvider#translateSalt()` which will convert the external form to the internal form.
 - `ABCDEFGHIJKLMN0PQRSTUVWXYZ` - the 12-44 character, Base64-encoded, unpadding, raw salt value. This decodes to a 8-32 byte salt used in the key derivation.
- PBKDF2
 - This KDF was added in v0.5.0.
 - [Password-Based Key Derivation Function 2](#) is an adaptive derivation function which uses an internal pseudorandom function (PRF) and iterates it many times over a password and salt (at least 16 bytes).
 - The PRF is recommended to be HMAC/SHA-256 or HMAC/SHA-512. The use of an HMAC cryptographic hash function mitigates a length extension attack.
 - The recommended minimum number of iterations is 160,000 (as of 2/1/2016 on commodity hardware). This number should be doubled every two years (see schedule below or use `PBKDF2CipherProviderGroovyTest#testDefaultConstructorShouldProvideStrongIter` to calculate safe minimums).
 - This KDF is not memory-hard (can be parallelized massively with commodity hardware) but is still recommended as sufficient by [NIST SP 800-132 \(PDF\)](#) and many cryptographers (when used with a proper iteration count and HMAC cryptographic hash function).
- None
 - This KDF was added in v0.5.0.
 - This KDF performs no operation on the input and is a marker to indicate the raw key is provided to the cipher. The key must be provided in hexadecimal encoding and be of a valid length for the associated cipher/algorithm.

1.1.5.1.1. Additional Resources

- [Explanation of optimal script cost parameters and relationships](#)

- [NIST Special Publication 800-132](#)
- [OWASP Password Storage Work Factor Calculations](#)
- [PBKDF2 rounds calculations](#)
- [Scrypt as KDF vs password storage vulnerabilities](#)
- [Scrypt vs. Bcrypt \(as of 2010\)](#)
- [Bcrypt vs PBKDF2](#)
- [Choosing a work factor for Bcrypt](#)
- [OpenSSL EVP BytesToKey PKCS#1v1.5](#)
- [OpenSSL KDF flaws description](#)


1.1.5.2. Salt and IV Encoding

Initially, the `EncryptContent` processor had a single method of deriving the encryption key from a user-provided password. This is now referred to as `NiFiLegacy` mode, effectively MD5 digest, 1000 iterations. In v0.4.0, another method of deriving the key, `OpenSSL PKCS#5 v1.5 EVP_BytesToKey` was added for compatibility with content encrypted outside of NiFi using the `openssl` command-line tool. Both of these [Key Derivation Functions](#) (KDF) had hard-coded digest functions and iteration counts, and the salt format was also hard-coded. With v0.5.0, additional KDFs are introduced with variable iteration counts, work factors, and salt formats. In addition, *raw keyed encryption* was also introduced. This required the capacity to encode arbitrary salts and Initialization Vectors (IV) into the cipher stream in order to be recovered by NiFi or a follow-on system to decrypt these messages.

For the existing KDFs, the salt format has not changed.


1.1.5.2.1. NiFi Legacy

The first 8 or 16 bytes of the input are the salt. The salt length is determined based on the selected algorithm's cipher block length. If the cipher block size cannot be determined (such as with a stream cipher like RC4), the default value of 8 bytes is used. On decryption, the salt is read in and combined with the password to derive the encryption key and IV.




1.1.5.2.2. OpenSSL PKCS#5 v1.5 EVP_BytesToKey

OpenSSL allows for salted or unsalted key derivation. **Unsalted key derivation is a security risk and is not recommended.** If a salt is present, the first 8 bytes of the input are the ASCII string "Salted_" (0x53 61 6C 74 65 64 5F 5F) and the next 8 bytes are the ASCII-encoded salt. On decryption, the salt is read in and combined with the password to derive the encryption key and IV. If there is no salt header, the entire input is considered to be the cipher text.



For new KDFs, each of which allow for non-deterministic IVs, the IV must be stored alongside the cipher text. This is not a vulnerability, as the IV is not required to be secret, but simply to be unique for messages encrypted using the same key to reduce the success of cryptographic attacks. For these KDFs, the output consists of the salt, followed by the salt delimiter, UTF-8 string "NiFiSALT" (0x4E 69 46 69 53 41 4C 54) and then the IV, followed by the IV delimiter, UTF-8 string "NiFiIV" (0x4E 69 46 69 49 56), followed by the cipher text.

1.1.5.2.3. Bcrypt, Scrypt, PBKDF2



```

0  24733024 65303830 31246E33 57743566  $s0$e0801$n3Wt5f
16 6C67776B 5961394A 586A4A41 67695A77  lgwkYa9JXjJAgiZw
32 4E694669 53414C54 C03A7A62 065CDC19  NiFiSALT.:zb \.
48 0726787A AEF3A9BC 4E694669 49561636  &xz...NiFiIV 6
64 FCCD26F5 49A04E43 559ED7AD A092A118  ..&.I.NCU.....
80 FEF2D480 0215A7F6 0C64B182 3FE4      .... .. d..?.

```

Signed Int big (select some data) 94 out of 94 bytes

```

0  B5B1AABC FB2BCEA1 EF81034A 493D9217  .....+.... JI=.
16 4E694669 53414C54 C6EE4F31 C34FEA86  NiFiSALT..01.0..
32 1F44B34F CEC9CAC7 4E694669 495678A3  D.O...NiFiIVx.
48 28E5D8FB F81800D5 4BF995A4 35136B53  (... .K...5 kS
64 C3DA8329 0D05BD90 AED1320F 97E4      ...) ....2 ..

```

Signed Int big (select some data) 78 out of 78 bytes

1.1.5.3. Java Cryptography Extension (JCE) Limited Strength Jurisdiction Policies

Because of US export regulations, default JVMs have [limits imposed on the strength of cryptographic operations](#) available to them. For example, AES operations are limited to 128 bit keys by default. While AES-128 is cryptographically safe, this can have unintended consequences, specifically on Password-based Encryption (PBE).

PBE is the process of deriving a cryptographic key for encryption or decryption from *user-provided secret material*, usually a password. Rather than a human remembering a (random-appearing) 32 or 64 character hexadecimal string, a password or passphrase is used.

A number of PBE algorithms provided by NiFi impose strict limits on the length of the password due to the underlying key length checks. Below is a table listing the maximum password length on a JVM with limited cryptographic strength.

Table 1.1. Table 1. Maximum Password Length on Limited Cryptographic Strength JVM

Algorithm	Max Password Length
PBEWITHMD5AND128BITAES-CBC-OPENSSL	16
PBEWITHMD5AND192BITAES-CBC-OPENSSL	16
PBEWITHMD5AND256BITAES-CBC-OPENSSL	16
PBEWITHMD5ANDDES	16
PBEWITHMD5ANDRC2	16
PBEWITHSHA1ANDRC2	16
PBEWITHSHA1ANDDES	16
PBEWITHSHAAND128BITAES-CBC-BC	7
PBEWITHSHAAND192BITAES-CBC-BC	7
PBEWITHSHAAND256BITAES-CBC-BC	7
PBEWITHSHAAND40BITRC2-CBC	7
PBEWITHSHAAND128BITRC2-CBC	7
PBEWITHSHAAND40BITRC4	7
PBEWITHSHAAND128BITRC4	7
PBEWITHSHA256AND128BITAES-CBC-BC	7
PBEWITHSHA256AND192BITAES-CBC-BC	7
PBEWITHSHA256AND256BITAES-CBC-BC	7
PBEWITHSHAAND2-KEYTRIPLEDES-CBC	7
PBEWITHSHAAND3-KEYTRIPLEDES-CBC	7
PBEWITHSHAANDTWOFISH-CBC	7

1.1.5.4. Allow Insecure Cryptographic Modes

By default, the `Allow Insecure Cryptographic Modes` property in `EncryptContent` processor settings is set to `not-allowed`. This means that if a password of fewer than 10 characters is provided, a validation error will occur. 10 characters is a conservative estimate and does not take into consideration full entropy calculations, patterns, etc.

Configure Processor

SETTINGS
SCHEDULING
PROPERTIES
COMMENTS

Required field +

Property	Value
Mode	? Encrypt
Key Derivation Function	? NiFi Legacy KDF
Encryption Algorithm	? MD5_128AES
Allow insecure cryptographic modes	? Not Allowed
Password	? No value set
Raw Key (hexadecimal)	? No value set
Public Keyring File	? No value set
Public Key User Id	? No value set
Private Keyring File	? No value set
Private Keyring Passphrase	? No value set

CANCEL APPLY

On a JVM with limited strength cryptography, some PBE algorithms limit the maximum password length to 7, and in this case it will not be possible to provide a "safe" password. It is recommended to install the JCE Unlimited Strength Jurisdiction Policy files for the JVM to mitigate this issue.

- [JCE Unlimited Strength Jurisdiction Policy files for Java 8](#)

If on a system where the unlimited strength policies cannot be installed, it is recommended to switch to an algorithm that supports longer passwords (see table above).

Allowing Weak Crypto If it is not possible to install the unlimited strength jurisdiction policies, the `Allow Weak Crypto` setting can be changed to `allowed`, but **this is not recommended**. Changing this setting explicitly acknowledges the inherent risk in using weak cryptographic configurations.

It is preferable to request upstream/downstream systems to switch to [keyed encryption](#) or use a "strong" [Key Derivation Function \(KDF\) supported by NiFi](#).

1.1.6. Encrypted Passwords in Configuration Files

In order to facilitate the secure setup of NiFi, you can use the `encrypt-config` command line utility to encrypt raw configuration values that NiFi decrypts in memory on startup. This extensible protection scheme transparently allows NiFi to use raw values in operation, while protecting them at rest. In the future, hardware security modules (HSM) and external

secure storage mechanisms will be integrated, but for now, an AES encryption provider is the default implementation.

This is a change in behavior; prior to 1.0, all configuration values were stored in plaintext on the file system. POSIX file permissions were recommended to limit unauthorized access to these files

If no administrator action is taken, the configuration values remain unencrypted.

1.1.6.1. Encrypt-Config Tool

The `encrypt-config` command line tool (invoked as `./bin/encrypt-config.sh` or `bin\encrypt-config.bat`) reads from a 'nifi.properties' file with plaintext sensitive configuration values, prompts for a master password or raw hexadecimal key, and encrypts each value. It replaces the plain values with the protected value in the same file, or writes to a new 'nifi.properties' file if specified.

The default encryption algorithm utilized is AES/GCM 128/256-bit. 128-bit is used if the JCE Unlimited Strength Cryptographic Jurisdiction Policy files are not installed, and 256-bit is used if they are installed.

You can use the following command line options with the `encrypt-config` tool:

- `-h,--help` Prints this usage message
- `-v,--verbose` Sets verbose mode (default false)
- `-n,--niFiProperties <arg>` The nifi.properties file containing unprotected config values (will be overwritten)
- `-l,--loginIdentityProviders <arg>` The login-identity-providers.xml file containing unprotected config values (will be overwritten)
- `-a,--authorizers <arg>` The authorizers.xml file containing unprotected config values (will be overwritten)
- `-f,--flowXml <arg>` The flow.xml.gz file currently protected with old password (will be overwritten)
- `-b,--bootstrapConf <arg>` The bootstrap.conf file to persist master key
- `-o,--outputNiFiProperties <arg>` The destination nifi.properties file containing protected config values (will not modify input nifi.properties)
- `-i,--outputLoginIdentityProviders <arg>` The destination login-identity-providers.xml file containing protected config values (will not modify input login-identity-providers.xml)
- `-u,--outputAuthorizers <arg>` The destination authorizers.xml file containing protected config values (will not modify input authorizers.xml)
- `-g,--outputFlowXml <arg>` The destination flow.xml.gz file containing protected config values (will not modify input flow.xml.gz)
- `-k,--key <arg>` The raw hexadecimal key to use to encrypt the sensitive properties

- `-e,--oldKey <arg>` The old raw hexadecimal key to use during key migration
- `-p,--password <arg>` The password from which to derive the key to use to encrypt the sensitive properties
- `-w,--oldPassword <arg>` The old password from which to derive the key during migration
- `-r,--useRawKey` If provided, the secure console will prompt for the raw key value in hexadecimal form
- `-m,--migrate` If provided, the `nifi.properties` and/or `login-identity-providers.xml` sensitive properties will be re-encrypted with a new key
- `-x,--encryptFlowXmlOnly` If provided, the properties in `flow.xml.gz` will be re-encrypted with a new key but the `nifi.properties` and/or `login-identity-providers.xml` files will not be modified
- `-s,--propsKey <arg>` The password or key to use to encrypt the sensitive processor properties in `flow.xml.gz`
- `-A,--newFlowAlgorithm <arg>` The algorithm to use to encrypt the sensitive processor properties in `flow.xml.gz`
- `-P,--newFlowProvider <arg>` The security provider to use to encrypt the sensitive processor properties in `flow.xml.gz`

As an example of how the tool works, assume that you have installed the tool on a machine supporting 256-bit encryption and with the following existing values in the 'nifi.properties' file:

```
# security properties #
nifi.sensitive.props.key=thisIsABadSensitiveKeyPassword
nifi.sensitive.props.algorithm=PBEWITHMD5AND256BITAES-CBC-OPENSSL
nifi.sensitive.props.provider=BC
nifi.sensitive.props.additional.keys=

nifi.security.keystore=/path/to/keystore.jks
nifi.security.keystoreType=JKS
nifi.security.keystorePasswd=thisIsABadKeystorePassword
nifi.security.keyPasswd=thisIsABadKeyPassword
nifi.security.truststore=
nifi.security.truststoreType=
nifi.security.truststorePasswd=
```

Enter the following arguments when using the tool:

```
encrypt-config.sh
-b bootstrap.conf
-k 0123456789ABCDEFEDCBA98765432100123456789ABCDEFEDCBA9876543210
-n nifi.properties
```

As a result, the 'nifi.properties' file is overwritten with protected properties and sibling encryption identifiers (`aes/gcm/256`, the currently supported algorithm):

```
# security properties #
```

```
nifi.sensitive.props.key=n2z+tTTbHuZ4V4V2||uWhdasyDXD4ZG21MAes/
vqh6u4vaz4xgL4aEbF4Y/dXevqk3ulRcOwflvc4RDQ==
nifi.sensitive.props.key.protected=aes/gcm/256
nifi.sensitive.props.algorithm=PBEWITHMD5AND256BITAES-CBC-OPENSSL
nifi.sensitive.props.provider=BC
nifi.sensitive.props.additional.keys=

nifi.security.keystore=/path/to/keystore.jks
nifi.security.keystoreType=JKS
nifi.security.keystorePasswd=oBjT92hIGRElIGOh||MZ6uYuWNBrOA6usq/
Jt3DaD2e4otNirZDytac/w/KFe0H0krJR03vcbo
nifi.security.keystorePasswd.protected=aes/gcm/256
nifi.security.keyPasswd=ac/BaE35SL/esLiJ||
+ULRvRLYdIDA2VqpE0eQXDEMjaLBMG2kbK0dOwBk/hGebDKlVg==
nifi.security.keyPasswd.protected=aes/gcm/256
nifi.security.truststore=
nifi.security.truststoreType=
nifi.security.truststorePasswd=
```

Additionally, the 'bootstrap.conf' file is updated with the encryption key as follows:

```
# Master key in hexadecimal format for encrypted sensitive configuration
values
nifi.bootstrap.sensitive.key=
0123456789ABCDEFEDCBA98765432100123456789ABCDEFEDCBA9876543210
```

Sensitive configuration values are encrypted by the tool by default, however you can encrypt any additional properties, if desired. To encrypt additional properties, specify them as comma-separated values in the `nifi.sensitive.props.additional.keys` property.

If the 'nifi.properties' file already has valid protected values, those property values are not modified by the tool.

When applied to 'login-identity-providers.xml' and 'authorizers.xml', the property elements are updated with an encryption attribute:

Example of protected login-identity-providers.xml:

```
<!-- LDAP Provider -->
<provider>
  <identifier>ldap-provider</identifier>
  <class>org.apache.nifi.ldap.LdapProvider</class>
  <property name="Authentication Strategy">START_TLS</property>
  <property name="Manager DN">someuser</property>
  <property name="Manager Password" encryption="aes/gcm/
128">q4r7WIgN0MaxdAKM||SGgdCTPGSFecuH4RraMYEdeyVb0x93abdWTVSWvhlw+k1A</
property>
  <property name="TLS - Keystore"></property>
  <property name="TLS - Keystore Password" encryption="aes/gcm/
128">Uah59TWX+Ru5GY5p||B44RT/LJtC08QWA5ehQf01JxIpf0qSJUzug25UwkF5a50g</
property>
  <property name="TLS - Keystore Type"></property>
  ...
</provider>
```

Example of protected authorizers.xml:

```
<!-- LDAP User Group Provider -->
```



```

<userGroupProvider>
  <identifier>ldap-user-group-provider</identifier>
  <class>org.apache.nifi.ldap.tenants.LdapUserGroupProvider</class>
  <property name="Authentication Strategy">START_TLS</property>
  <property name="Manager DN">someuser</property>
  <property name="Manager Password" encryption="aes/gcm/
128">q4r7WIGN0MaxdAKM| |SGgdCTPGSFecuH4RraMYEdeyVb0x93abdWTVSWvhlw+klA</
property>
  <property name="TLS - Keystore"></property>
  <property name="TLS - Keystore Password" encryption="aes/gcm/
128">Uah59Twx+Ru5GY5p| |B44RT/LJtC08QWA5ehQf01JxIpf0qSJUZug25UwkF5a50g</
property>
  <property name="TLS - Keystore Type"></property>
  ...
</userGroupProvider>
---
```

1.1.6.2. Sensitive Property Key Migration

In order to change the key used to encrypt the sensitive values, indicate **migration mode** using the `-m` or `--migrate` flag, provide the new key or password using the `-k` or `-p` flags as usual, and provide the existing key or password using `-e` or `-w` respectively. This will allow the toolkit to decrypt the existing values and re-encrypt them, and update `bootstrap.conf` with the new key. Only one of the key or password needs to be specified for each phase (old vs. new), and any combination is sufficient:

- old key # new key
- old key # new password
- old password # new key
- old password # new password

1.1.6.3. Existing Flow Migration

This tool can also be used to change the value of `nifi.sensitive.props.key` for an existing flow. The tool will read the existing `flow.xml.gz` and decrypt any sensitive component properties using the original key, then re-encrypt the sensitive properties with the new key, and write out a new version of the `flow.xml.gz`, or overwrite the existing one.

The current sensitive properties key is not provided as a command-line argument, as it is read directly from `nifi.properties`. As this file is a required parameter, the `-x/--encryptFlowXmlOnly` flags tell the tool **not** to attempt to encrypt the properties in `nifi.properties`, but rather to **only** update the `nifi.sensitive.props.key` value with the new key. The exception to this is if the `nifi.properties` is **already** encrypted, the new sensitive property key will also be encrypted before being written to `nifi.properties`.

The following command would migrate the sensitive properties key in place, meaning it would overwrite the existing `flow.xml.gz` and `nifi.properties`:

```
./encrypt-config.sh -f /path/to/flow.xml.gz -n ./path/to/nifi.properties -s
newpassword -x
```

The following command would migrate the sensitive properties key and write out a separate `flow.xml.gz` and `nifi.properties`:

```
./encrypt-config.sh -f ./path/to/src/flow.xml.gz -g /path/to/dest/flow.xml.gz -n /path/to/src/nifi.properties -o /path/to/dest/nifi.properties -s newpassword -x
```

1.1.6.4. Password Key Derivation

Instead of providing a 32 or 64 character raw hexadecimal key, you can provide a password from which the key will be derived. As of 1.0.0, the password must be at least 12 characters, and the key will be derived using `SCrypt` with the parameters:

- `pw` - the password bytes in UTF-8
- `salt` - the fixed salt value (`NIFI_SCRYPT_SALT`) bytes in UTF-8
- `N` - 2^{16}
- `r` - 8
- `p` - 1
- `dkLen` - determined by the JCE policies available

As of August 2016, these values are determined to be strong for this threat model but may change in future versions.

While fixed salts are counter to best practices, a static salt is necessary for deterministic key derivation without additional storage of the salt value.

1.1.6.5. Secure Prompt

If you prefer not to provide the password or raw key in the command-line invocation of the tool, leaving these arguments absent will prompt a secure console read of the password (by default) or raw key (if the `-r` flag is provided at invocation).

1.1.7. Administrative Tools

The admin toolkit contains command line utilities for administrators to support NiFi maintenance in standalone and clustered environments. These utilities include:

- **Notify** - The notification tool allows administrators to send bulletins to the NiFi UI using the command line.
- **Node Manager** - The node manager tool allows administrators to perform a status check on a node as well as to connect, disconnect, or remove nodes that are part of a cluster.
- **File Manager** - The file manager tool allows administrators to backup, install or restore a NiFi installation from backup.

The admin toolkit is bundled with the `nifi-toolkit` and can be executed with scripts found in the `bin` folder.

1.1.7.1. Prerequisites for Running Admin Toolkit in a Secure Environment

For secured nodes and clusters, two policies should be configured in advance:

- Access the controller - A user that will have access to these utilities should be authorized in NiFi by creating an "access the controller" policy (`/controller`) with both view and modify rights.
- Proxy user request - If not previously set node's identity (the DN value of the node's certificate) should be authorized to proxy requests on behalf of a user

When executing either the notify or node manager tools in a secured environment the `proxyDN` flag option should be used in order to properly identify the user that was authorized to execute these commands. In non-secure environments, or if running the status operation on the Node Manager tool, the flag is ignored.

1.1.7.2. Notify

Notify allows administrators to send messages as bulletins to NiFi. Notify is supported on NiFi version 1.2.0 and higher. The notification tool is also available in a `notify.bat` file for use on Windows machines.

To send notifications:

```
notify.sh -d {$NIFI_HOME} -b {nifi bootstrap file path} -m {message} [-l
{level}] [-v]
```

To show help:

```
notify.sh -h
```

The following are available options:

- `-b,--bootstrapConf <arg>` Existing Bootstrap Configuration file (required)
- `-d,--nifiInstallDir <arg>` NiFi Root Folder (required)
- `-h,--help` Help Text (optional)
- `-l,--level <arg>` Status level of bulletin - INFO, WARN, ERROR
- `-m,--message <arg>` Bulletin message (required)
- `-p,--proxyDN <arg>` Proxy or User DN (required for secured nodes)
- `-v,--verbose` Verbose messaging (optional)


Example usage on Linux:

```
./notify.sh -d /usr/nifi/nifi_current -b /usr/nifi/nifi_current/conf/
bootstrap.conf -m "Test Message Server 1" -l "WARN" -p "ydavis@nifi" -v
```

Example usage on Windows:

```
notify.bat -v -d "C:\\Program Files\\nifi\\nifi-1.2.0-SNAPSHOT" -b "C:\\Program Files\\nifi\\nifi-1.2.0-SNAPSHOT\\conf\\bootstrap.conf" -m "Test Message Server 1" -v
```

Executing the above command line should result in a bulletin appearing in NiFi:



1.1.7.3. Node Manager

Node manager supports connecting, disconnecting and removing a node when in a cluster (an error message displays if the node is not part of a cluster) as well as obtaining the status of a node. When nodes are disconnected from a cluster and need to be connected or removed, a list of urls of connected nodes should be provided to send the required command to the active cluster. Node Manager supports NiFi version 1.0.0 and higher. Node Manager is also available in 'node-manager.bat' file for use on Windows machines.

To connect, disconnect, or remove a node from a cluster:

```
node-manager.sh -d {$NIFI_HOME} -b { nifi bootstrap file path}
-o {remove|disconnect|connect|status} [-u {url list}] [-p {proxy name}] [-v]
```

To show help:

```
node-manager.sh -h
```

The following are available options:

- `-b, --bootstrapConf <arg>` Existing Bootstrap Configuration file (required)
- `-d, --nifiInstallDir <arg>` NiFi Root Folder (required)
- `-h, --help` Help Text (optional)
- `-o, --operation <arg>` Operations supported: status, connect (cluster), disconnect (cluster), remove (cluster)
- `-p, --proxyDN <arg>` Proxy or User DN (required for secured nodes doing connect, disconnect and remove operations)
- `-u, --clusterUrls <arg>` Comma delimited list of active urls for cluster (optional). Not required for disconnecting a node yet will be needed when connecting or removing from a cluster

- `-v, --verbose` Verbose messaging (optional)

Example usage on Linux:

```
# disconnect without cluster url list
./node-manager.sh
-d /usr/nifi/nifi_current
-b /usr/nifi/nifi_current/conf/bootstrap.conf
-o disconnect
-p ydavis@nifi
-v
```

```
#with url list
./node-manager.sh
-d /usr/nifi/nifi_current
-b /usr/nifi/nifi_current/conf/bootstrap.conf
-o connect
-u 'http://nifi-server-1:8080,http://nifi-server-2:8080'
-v
```

Example usage on Windows:

```
node-manager.bat
-d "C:\\Program Files\\nifi\\nifi-1.2.0-SNAPSHOT"
-b "C:\\Program Files\\nifi\\nifi-1.2.0-SNAPSHOT\\conf\\bootstrap.conf"
-o disconnect
-v
```

1.1.7.3.1. Expected behavior

Status:

To obtain information on UI availability of a node, the status operation can be used to determine if the node is running. If the `-u (clusterUrls)` option is not provided the current node url is checked otherwise the urls provided will be checked.

Disconnect:

When a node is disconnected from the cluster, the node itself should appear as disconnected and the cluster should have a bulletin indicating the disconnect request was received. The cluster should also show $n-1/n$ nodes available in the cluster. For example, if 1 node is disconnected from a 3-node cluster, then 2 of 3 nodes should show on the remaining nodes in the cluster. Changes to the flow should not be allowed on the cluster with a disconnected node.

Connect:

When the connect command is executed to reconnect a node to a cluster, upon completion the node itself should show that it has rejoined the cluster by showing n/n nodes. Previously it would have shown Disconnected. Other nodes in the cluster should receive a bulletin of the connect request and also show n/n nodes allowing for changes to be allowed to the flow.

Remove:

When the remove command is executed the node should show as disconnected from a cluster. The nodes remaining in the cluster should show $n-1/n-1$ nodes. For example, if 1 node is removed from a 3-node cluster, then the remaining 2 nodes should show 2 of 2

nodes). The cluster should allow a flow to be adjusted. The removed node can rejoin the cluster if restarted and the flow for the cluster has not changed. If the flow was changed, the flow template of the removed node should be deleted before restarting the node to allow it to obtain the cluster flow (otherwise an uninherited flow file exception may occur).

1.1.7.4. File Manager

The File Manager utility allows system administrators to take a backup of an existing NiFi installation, install a new version of NiFi in a designated location (while migrating any previous configuration settings) or restore an installation from a previous backup. File Manager supports NiFi version 1.0.0 and higher and is available in 'file-manager.bat' file for use on Windows machines.

To show help:

```
file-manager.sh -h
```

The following are available options:

- `-b,--backupDir <arg>` Backup NiFi Directory (used with backup or restore operation)
- `-c,--nifiCurrentDir <arg>` Current NiFi Installation Directory (used optionally with install or restore operation)
- `-d,--nifiInstallDir <arg>` NiFi Installation Directory (used with install or restore operation)
- `-h,--help` Print help info (optional)
- `-i,--installFile <arg>` NiFi Install File (used with install operation)
- `-m,--moveRepositories` Allow repositories to be moved to new/restored nifi directory from existing installation, if available (used optionally with install or restore operation)
- `-o,--operation <arg>` File operation (install | backup | restore)
- `-r,--nifiRollbackDir <arg>` NiFi Installation Directory (used with install or restore operation)
- `-t,--bootstrapConf <arg>` Current NiFi Bootstrap Configuration File (used optionally)
- `-v,--verbose` Verbose messaging (optional)
- `-x,--overwriteConfigs` Overwrite existing configuration directory with upgrade changes (used optionally with install or restore operation)

Example usage on Linux:

```
# backup NiFi installation
# option -t may be provided to ensure backup of external bootstrap.conf file
./file-manager.sh
-o backup
-b /tmp/nifi_bak
```

```
-c /usr/nifi_old
-v

# install NiFi using compressed tar file into /usr/nifi directory (should
  install as /usr/nifi/nifi-1.3.0).
# migrate existing configurations with location determined by external
  bootstrap.conf and move over repositories from nifi_old
# options -t and -c should both be provided if migration of configurations,
  state and repositories are required
./file-manager.sh
-o install
-i nifi-1.3.0.tar.gz
-d /usr/nifi
-c /usr/nifi/nifi_old
-t /usr/nifi/old_conf/bootstrap.conf
-v
-m

# restore NiFi installation from backup directory and move back repositories
# option -t may be provided to ensure bootstrap.conf is restored to the file
  path provided, otherwise it is placed in the
# default directory under the rollback path (e.g. /usr/nifi_old/conf)
./file-manager.sh
-o restore
-b /tmp/nifi_bak
-r /usr/nifi_old
-c /usr/nifi
-m
-v
```

1.1.7.5. Expected Behavior

Backup:

During the backup operation a backup directory is created in a designated location for an existing NiFi installation. Backups will capture all critical files (including any internal or external configurations, libraries, scripts and documents) however it excludes backing up repositories and logs due to potential size. If configuration/library files are external from the existing installation folder the backup operation will capture those as well.

Install:


During the install operation File Manager will perform installation using the designated NiFi binary file (either tar.gz or zip file) to create a new installation or migrate an existing nifi installation to a new one. Installation can optionally move repositories (if located within the configuration folder of the current installation) to the new installation as well as migrate configuration files to the newer installation.

Restore:

The restore operation allows an existing installation to revert back to a previous installation. Using an existing backup directory (created from the backup operation) the FileManager utility will restore libraries, scripts and documents as well as revert to previous configurations. NOTE: If repositories were changed due to the installation of a newer version of NiFi these may no longer be compatible during restore. In that scenario exclude the -m option to ensure new repositories will be created or, if repositories live outside of the NiFi directory, remove them so they can be recreated on startup after restore.

1.1.8. Clustering Configuration

This section provides a quick overview of NiFi Clustering and instructions on how to set up a basic cluster. In the future, we hope to provide supplemental documentation that covers the NiFi Cluster Architecture in depth.



NiFi employs a Zero-Master Clustering paradigm. Each node in the cluster performs the same tasks on the data, but each operates on a different set of data. One of the nodes is automatically elected (via Apache ZooKeeper) as the Cluster Coordinator. All nodes in the cluster will then send heartbeat/status information to this node, and this node is responsible for disconnecting nodes that do not report any heartbeat status for some amount of time. Additionally, when a new node elects to join the cluster, the new node must first connect to the currently-elected Cluster Coordinator in order to obtain the most up-to-date flow. If the Cluster Coordinator determines that the node is allowed to join (based on its configured Firewall file), the current flow is provided to that node, and that node is able to join the cluster, assuming that the node's copy of the flow matches the copy provided by the Cluster Coordinator. If the node's version of the flow configuration differs from that of the Cluster Coordinator's, the node will not join the cluster.

Why Cluster?

NiFi Administrators or Dataflow Managers (DFMs) may find that using one instance of NiFi on a single server is not enough to process the amount of data they have. So, one solution is to run the same dataflow on multiple NiFi servers. However, this creates a management problem, because each time DFMs want to change or update the dataflow, they must make those changes on each server and then monitor each server individually. By clustering the NiFi servers, it's possible to have that increased processing capability along with a single interface through which to make dataflow changes and monitor the dataflow. Clustering allows the DFM to make each change only once, and that change is then replicated to all the nodes of the cluster. Through the single interface, the DFM may also monitor the health and status of all the nodes.

NiFi Clustering is unique and has its own terminology. It's important to understand the following terms before setting up a cluster.

Terminology

NiFi Cluster Coordinator: A NiFi Cluster Coordinator is the node in a NiFi cluster that is responsible for carrying out tasks to manage which nodes are allowed in the cluster and providing the most up-to-date flow to newly joining nodes. When a DataFlow Manager manages a dataflow in a cluster, they are able to do so through the User Interface of any node in the cluster. Any change made is then replicated to all nodes in the cluster.

Nodes: Each cluster is made up of one or more nodes. The nodes do the actual data processing.

Primary Node: Every cluster has one Primary Node. On this node, it is possible to run "Isolated Processors" (see below). ZooKeeper is used to automatically elect a Primary Node. If that node disconnects from the cluster for any reason, a new Primary Node will automatically be elected. Users can determine which node is currently elected as the Primary Node by looking at the Cluster Management page of the User Interface.

Isolated Processors: In a NiFi cluster, the same dataflow runs on all the nodes. As a result, every component in the flow runs on every node. However, there may be cases when the DFM would not want every processor to run on every node. The most common case is when using a processor that communicates with an external service using a protocol that does not scale well. For example, the GetSFTP processor pulls from a remote directory, and if the GetSFTP Processor runs on every node in the cluster tries simultaneously to pull from the same remote directory, there could be race conditions. Therefore, the DFM could configure the GetSFTP on the Primary Node to run in isolation, meaning that it only runs on that node. It could pull in data and - with the proper dataflow configuration - load-balance it across the rest of the nodes in the cluster. Note that while this feature exists, it is also very common to simply use a standalone NiFi instance to pull data and feed it to the cluster. It just depends on the resources available and how the Administrator decides to configure the cluster.

Heartbeats: The nodes communicate their health and status to the currently elected Cluster Coordinator via "heartbeats", which let the Coordinator know they are still connected to the cluster and working properly. By default, the nodes emit heartbeats every 5 seconds, and if the Cluster Coordinator does not receive a heartbeat from a node within 40 seconds, it disconnects the node due to "lack of heartbeat". (The 5-second setting is configurable in the *nifi.properties* file. See the [System Properties](#) section of this document for more information.) The reason that the Cluster Coordinator disconnects the node is because the Coordinator needs to ensure that every node in the cluster is in sync, and if a node is not heard from regularly, the Coordinator cannot be sure it is still in sync with the rest of the cluster. If, after 40 seconds, the node does send a new heartbeat, the Coordinator will automatically request that the node re-join the cluster, to include the re-validation of the node's flow. Both the disconnection due to lack of heartbeat and the reconnection once a heartbeat is received are reported to the DFM in the User Interface.

Communication within the Cluster

As noted, the nodes communicate with the Cluster Coordinator via heartbeats. When a Cluster Coordinator is elected, it updates a well-known ZNode in Apache ZooKeeper with

its connection information so that nodes understand where to send heartbeats. If one of the nodes goes down, the other nodes in the cluster will not automatically pick up the load of the missing node. It is possible for the DFM to configure the dataflow for failover contingencies; however, this is dependent on the dataflow design and does not happen automatically.

When the DFM makes changes to the dataflow, the node that receives the request to change the flow communicates those changes to all nodes and waits for each node to respond, indicating that it has made the change on its local flow.

Dealing with Disconnected Nodes

A DFM may manually disconnect a node from the cluster. But if a node becomes disconnected for any other reason (such as due to lack of heartbeat), the Cluster Coordinator will show a bulletin on the User Interface. The DFM will not be able to make any changes to the dataflow until the issue of the disconnected node is resolved. The DFM or the Administrator will need to troubleshoot the issue with the node and resolve it before any new changes may be made to the dataflow. However, it is worth noting that just because a node is disconnected does not mean that it is not working; this may happen for a few reasons, including that the node is unable to communicate with the Cluster Coordinator due to network problems.

There are cases where a DFM may wish to continue making changes to the flow, even though a node is not connected to the cluster. In this case, they DFM may elect to remove the node from the cluster entirely through the Cluster Management dialog. Once removed, the node cannot be rejoined to the cluster until it has been restarted.

Flow Election

When a cluster first starts up, NiFi must determine which of the nodes have the "correct" version of the flow. This is done by voting on the flows that each of the nodes has. When a node attempts to connect to a cluster, it provides a copy of its local flow to the Cluster Coordinator. If no flow has yet been elected the "correct" flow, the node's flow is compared to each of the other Nodes' flows. If another Node's flow matches this one, a vote is cast for this flow. If no other Node has reported the same flow yet, this flow will be added to the pool of possibly elected flows with one vote. After some amount of time has elapsed (configured by setting the `nifi.cluster.flow.election.max.wait.time` property) or some number of Nodes have cast votes (configured by setting the `nifi.cluster.flow.election.max.candidates` property), a flow is elected to be the "correct" copy of the flow. All nodes that have incompatible flows are then disconnected from the cluster while those with compatible flows inherit the cluster's flow. Election is performed according to the "popular vote" with the caveat that the winner will never be an "empty flow" unless all flows are empty. This allows an administrator to remove a node's `flow.xml.gz` file and restart the node, knowing that the node's flow will not be voted to be the "correct" flow unless no other flow is found.

Basic Cluster Setup

This section describes the setup for a simple three-node, non-secure cluster comprised of three instances of NiFi.

For each instance, certain properties in the `nifi.properties` file will need to be updated. In particular, the Web and Clustering properties should be evaluated for your situation and adjusted accordingly. All the properties are described in the [System Properties](#) section of

this guide; however, in this section, we will focus on the minimum properties that must be set for a simple cluster.

For all three instances, the Cluster Common Properties can be left with the default settings. Note, however, that if you change these settings, they must be set the same on every instance in the cluster.


For each Node, the minimum properties to configure are as follows:

- Under the *Web Properties* section, set either the http or https port that you want the Node to run on. Also, consider whether you need to set the http or https host property.
- Under the *State Management* section, set the `nifi.state.management.provider.cluster` property to the identifier of the Cluster State Provider. Ensure that the Cluster State Provider has been configured in the `state-management.xml` file. See [Configuring State Providers](#) for more information.
- Under *Cluster Node Properties*, set the following:
 - `nifi.cluster.is.node` - Set this to `true`.
 - `nifi.cluster.node.address` - Set this to the fully qualified hostname of the node. If left blank, it defaults to "localhost".
 - `nifi.cluster.node.protocol.port` - Set this to an open port that is higher than 1024 (anything lower requires root).
 - `nifi.cluster.node.protocol.threads` - The number of threads that should be used to communicate with other nodes in the cluster. This property defaults to 10. A thread pool is used for replicating requests to all nodes, and the thread pool will never have fewer than this number of threads. It will grow as needed up to the maximum value set by the `nifi.cluster.node.protocol.max.threads` property.
 - `nifi.cluster.node.protocol.max.threads` - The maximum number of threads that should be used to communicate with other nodes in the cluster. This property defaults to 50. A thread pool is used for replication requests to all nodes, and the thread pool will have a "core" size that is configured by the `nifi.cluster.node.protocol.threads` property. However, if necessary, the thread pool will increase the number of active threads to the limit set by this property.
 - `nifi.zookeeper.connect.string` - The Connect String that is needed to connect to Apache ZooKeeper. This is a comma-separated list of hostname:port pairs. For example, `localhost:2181,localhost:2182,localhost:2183`. This should contain a list of all ZooKeeper instances in the ZooKeeper quorum.
 - `nifi.zookeeper.root.node` - The root ZNode that should be used in ZooKeeper. ZooKeeper provides a directory-like structure for storing data. Each 'directory' in this structure is referred to as a ZNode. This denotes the root ZNode, or 'directory', that should be used for storing data. The default value is `/root`. This is important to set correctly, as which cluster the NiFi instance attempts to join is determined by which ZooKeeper instance it connects to and the ZooKeeper Root Node that is specified.
 - `nifi.cluster.flow.election.max.wait.time` - Specifies the amount of time to wait before electing a Flow as the "correct" Flow. If the number

of Nodes that have voted is equal to the number specified by the `nifi.cluster.flow.election.max.candidates` property, the cluster will not wait this long. The default value is `5 mins`. Note that the time starts as soon as the first vote is cast.

- `nifi.cluster.flow.election.max.candidates` - Specifies the number of Nodes required in the cluster to cause early election of Flows. This allows the Nodes in the cluster to avoid having to wait a long time before starting processing if we reach at least this number of nodes in the cluster.

Now, it is possible to start up the cluster. It does not matter which order the instances start up. Navigate to the URL for one of the nodes, and the User Interface should look similar to the following:



Troubleshooting

If you encounter issues and your cluster does not work as described, investigate the `nifi-app.log` and `nifi-user.log` files on the nodes. If needed, you can change the logging level to `DEBUG` by editing the `conf/logback.xml` file. Specifically, set the `level="DEBUG"` in the following line (instead of `"INFO"`):

```
<logger name="org.apache.nifi.web.api.config" level="INFO" additivity="false">
  <appender-ref ref="USER_FILE"/>
</logger>
```

1.1.9. State Management

NiFi provides a mechanism for Processors, Reporting Tasks, Controller Services, and the framework itself to persist state. This allows a Processor, for example, to resume from the place where it left off after NiFi is restarted. Additionally, it allows for a Processor to store some piece of information so that the Processor can access that information from all of the different nodes in the cluster. This allows one node to pick up where another node left off, or to coordinate across all of the nodes in a cluster.

1.1.9.1. Configuring State Providers

When a component decides to store or retrieve state, it does so by providing a `"Scope"` - either `Node-local` or `Cluster-wide`. The mechanism that is used to store and retrieve this state is then determined based on this `Scope`, as well as the configured State Providers. The `nifi.properties` file contains three different properties that are relevant to configuring these State Providers.

Property	Description
nifi.state.management.configuration.file	The first is the property that specifies an external XML file that is used for configuring the local and/or cluster-wide State Providers. This XML file may contain configurations for multiple providers
nifi.state.management.provider.local	The property that provides the identifier of the local State Provider configured in this XML file
nifi.state.management.provider.cluster	Similarly, the property provides the identifier of the cluster-wide State Provider configured in this XML file.

This XML file consists of a top-level `state-management` element, which has one or more `local-provider` and zero or more `cluster-provider` elements. Each of these elements then contains an `id` element that is used to specify the identifier that can be referenced in the `nifi.properties` file, as well as a `class` element that specifies the fully-qualified class name to use in order to instantiate the State Provider. Finally, each of these elements may have zero or more `property` elements. Each `property` element has an attribute, `name` that is the name of the property that the State Provider supports. The textual content of the property element is the value of the property.

Once these State Providers have been configured in the `state-management.xml` file (or whatever file is configured), those Providers may be referenced by their identifiers.

By default, the Local State Provider is configured to be a `WriteAheadLocalStateProvider` that persists the data to the `$NIFI_HOME/state/local` directory. The default Cluster State Provider is configured to be a `ZooKeeperStateProvider`. The default ZooKeeper-based provider must have its `Connect String` property populated before it can be used. It is also advisable, if multiple NiFi instances will use the same ZooKeeper instance, that the value of the `Root Node` property be changed. For instance, one might set the value to `/nifi/<team name>/production`. A `Connect String` takes the form of comma separated `<host>:<port>` tuples, such as `my-zk-server1:2181,my-zk-server2:2181,my-zk-server3:2181`. In the event a port is not specified for any of the hosts, the ZooKeeper default of 2181 is assumed.

When adding data to ZooKeeper, there are two options for Access Control: `Open` and `CreatorOnly`. If the `Access Control` property is set to `Open`, then anyone is allowed to log into ZooKeeper and have full permissions to see, change, delete, or administer the data. If `CreatorOnly` is specified, then only the user that created the data is allowed to read, change, delete, or administer the data. In order to use the `CreatorOnly` option, NiFi must provide some form of authentication. See the [ZooKeeper Access Control](#) section below for more information on how to configure authentication.

If NiFi is configured to run in a standalone mode, the `cluster-provider` element need not be populated in the `state-management.xml` file and will actually be ignored if they are populated. However, the `local-provider` element must always be present and populated. Additionally, if NiFi is run in a cluster, each node must also have the `cluster-provider` element present and properly configured. Otherwise, NiFi will fail to startup.

While there are not many properties that need to be configured for these providers, they were externalized into a separate `state-management.xml` file, rather than being configured via the `nifi.properties` file, simply because different implementations may require different properties, and it is easier to maintain and understand the configuration in an XML-based file such as this, than to mix the properties of the Provider in with all of the other NiFi framework-specific properties.

It should be noted that if Processors and other components save state using the Clustered scope, the Local State Provider will be used if the instance is a standalone instance (not in a cluster) or is disconnected from the cluster. This also means that if a standalone instance is migrated to become a cluster, then that state will no longer be available, as the component will begin using the Clustered State Provider instead of the Local State Provider.

1.1.9.2. Embedded ZooKeeper Server

As mentioned above, the default State Provider for cluster-wide state is the `ZooKeeperStateProvider`. At the time of this writing, this is the only State Provider that exists for handling cluster-wide state. What this means is that NiFi has dependencies on ZooKeeper in order to behave as a cluster. However, there are many environments in which NiFi is deployed where there is no existing ZooKeeper ensemble being maintained. In order to avoid the burden of forcing administrators to also maintain a separate ZooKeeper instance, NiFi provides the option of starting an embedded ZooKeeper server.

Property	Description
<code>nifi.state.management.embedded.zookeeper.start</code>	Specifies whether or not this instance of NiFi should run an embedded ZooKeeper server
<code>nifi.state.management.embedded.zookeeper.properties</code>	Properties file that provides the ZooKeeper properties to use if <code>nifi.state.management.embedded.zookeeper.start</code> is set to <code>true</code>

This can be accomplished by setting the `nifi.state.management.embedded.zookeeper.start` property in `nifi.properties` to `true` on those nodes that should run the embedded ZooKeeper server. Generally, it is advisable to run ZooKeeper on either 3 or 5 nodes. Running on fewer than 3 nodes provides less durability in the face of failure. Running on more than 5 nodes generally produces more network traffic than is necessary. Additionally, running ZooKeeper on 4 nodes provides no more benefit than running on 3 nodes, ZooKeeper requires a majority of nodes be active in order to function. However, it is up to the administrator to determine the number of nodes most appropriate to the particular deployment of NiFi.

If the `nifi.state.management.embedded.zookeeper.start` property is set to `true`, the `nifi.state.management.embedded.zookeeper.properties` property in `nifi.properties` also becomes relevant. This specifies the ZooKeeper properties file to use. At a minimum, this properties file needs to be populated with the list of ZooKeeper servers. The servers are specified as properties in the form of `server.1, server.2, to server.n`. Each of these servers is configured as `<hostname>:<quorum port>[:<leader election port>]`. For example, `myhost:2888:3888`. This list of nodes should be the same nodes in the NiFi cluster that have the `nifi.state.management.embedded.zookeeper.start` property set to `true`. Also note that because ZooKeeper will be listening on these ports, the firewall may need to be configured to open these ports for incoming traffic, at least between nodes in the cluster. Additionally, the port to listen on for client connections must be opened in the firewall. The default value for this is `2181` but can be configured via the `clientPort` property in the `zookeeper.properties` file.

When using an embedded ZooKeeper, the `./conf/zookeeper.properties` file has a property named `dataDir`. By default, this value is set to `./state/zookeeper`. If more than one NiFi node is running an embedded ZooKeeper, it is important to tell the server which one it is. This is accomplished by creating a file named `myid` and placing it in ZooKeeper's data directory. The contents of this file should be the index of the server as specific by

the server.<number>. So for one of the ZooKeeper servers, we will accomplish this by performing the following commands:

```
cd $NIFI_HOME
mkdir state
mkdir state/zookeeper
echo 1 > state/zookeeper/myid
```

For the next NiFi Node that will run ZooKeeper, we can accomplish this by performing the following commands:

```
cd $NIFI_HOME
mkdir state
mkdir state/zookeeper
echo 2 > state/zookeeper/myid
```

And so on.

For more information on the properties used to administer ZooKeeper, see the [ZooKeeper Admin Guide](#).

For information on securing the embedded ZooKeeper Server, see the [Securing ZooKeeper](#) section below.

1.1.9.3. ZooKeeper Access Control

ZooKeeper provides Access Control to its data via an Access Control List (ACL) mechanism. When data is written to ZooKeeper, NiFi will provide an ACL that indicates that any user is allowed to have full permissions to the data, or an ACL that indicates that only the user that created the data is allowed to access the data. Which ACL is used depends on the value of the `Access Control` property for the `ZooKeeperStateProvider` (see the [Configuring State Providers](#) section for more information).

In order to use an ACL that indicates that only the Creator is allowed to access the data, we need to tell ZooKeeper who the Creator is. There are two mechanisms for accomplishing this. The first mechanism is to provide authentication using Kerberos. See [Kerberizing NiFi's ZooKeeper Client](#) for more information.

The second option is to use a user name and password. This is configured by specifying a value for the `Username` and a value for the `Password` properties for the `ZooKeeperStateProvider` (see the [Configuring State Providers](#) section for more information). The important thing to keep in mind here, though, is that ZooKeeper will pass around the password in plain text. This means that using a user name and password should not be used unless ZooKeeper is running on localhost as a one-instance cluster, or if communications with ZooKeeper occur only over encrypted communications, such as a VPN or an SSL connection. ZooKeeper will be providing support for SSL connections in version 3.5.0.

1.1.9.4. Securing ZooKeeper

When NiFi communicates with ZooKeeper, all communications, by default, are non-secure, and anyone who logs into ZooKeeper is able to view and manipulate all of the NiFi state that is stored in ZooKeeper. To prevent this, we can use Kerberos to manage the authentication. At this time, ZooKeeper does not provide support for encryption via SSL.

Support for SSL in ZooKeeper is being actively developed and is expected to be available in the 3.5.x release version.

In order to secure the communications, we need to ensure that both the client and the server support the same configuration. Instructions for configuring the NiFi ZooKeeper client and embedded ZooKeeper server to use Kerberos are provided below.

If Kerberos is not already setup in your environment, you can find information on installing and setting up a Kerberos Server at https://access.redhat.com/documentation/en-US/Red_Hat_Enterprise_Linux/6/html/Managing_Smart_Cards/Configuring_a_Kerberos_5_Server.html. This guide assumes that Kerberos already has been installed in the environment in which NiFi is running.

Note, the following procedures for kerberizing an Embedded ZooKeeper server in your NiFi Node and kerberizing a ZooKeeper NiFi client will require that Kerberos client libraries be installed. This is accomplished in Fedora-based Linux distributions via:

```
yum install krb5-workstation
```

Once this is complete, the `/etc/krb5.conf` will need to be configured appropriately for your organization's Kerberos environment.

1.1.9.4.1. Kerberizing Embedded ZooKeeper Server

The `krb5.conf` file on the systems with the embedded zookeeper servers should be identical to the one on the system where the `krb5kdc` service is running. When using the embedded ZooKeeper server, we may choose to secure the server by using Kerberos. All nodes configured to launch an embedded ZooKeeper and using Kerberos should follow these steps. When using the embedded ZooKeeper server, we may choose to secure the server by using Kerberos. All nodes configured to launch an embedded ZooKeeper and using Kerberos should follow these steps.

In order to use Kerberos, we first need to generate a Kerberos Principal for our ZooKeeper servers. The following command is run on the server where the `krb5kdc` service is running. This is accomplished via the `kadmin` tool:

```
kadmin: addprinc "zookeeper/myHost.example.com@EXAMPLE.COM"
```

Here, we are creating a Principal with the primary `zookeeper/myHost.example.com`, using the realm `EXAMPLE.COM`. We need to use a Principal whose name is `<service name>/<instance name>`. In this case, the service is `zookeeper` and the instance name is `myHost.example.com` (the fully qualified name of our host).

Next, we will need to create a KeyTab for this Principal, this command is run on the server with the NiFi instance with an embedded zookeeper server:

```
kadmin: xst -k zookeeper-server.keytab zookeeper/myHost.example.com@EXAMPLE.COM
```

This will create a file in the current directory named `zookeeper-server.keytab`. We can now copy that file into the `$NIFI_HOME/conf/` directory. We should ensure that only the user that will be running NiFi is allowed to read this file.

We will need to repeat the above steps for each of the instances of NiFi that will be running the embedded ZooKeeper server, being sure to replace `myHost.example.com` with

myHost2.example.com, or whatever fully qualified hostname the ZooKeeper server will be run on.

Now that we have our KeyTab for each of the servers that will be running NiFi, we will need to configure NiFi's embedded ZooKeeper server to use this configuration. ZooKeeper uses the Java Authentication and Authorization Service (JAAS), so we need to create a JAAS-compatible file In the `$NIFI_HOME/conf/` directory, create a file named `zookeeper-jaas.conf` (this file will already exist if the Client has already been configured to authenticate via Kerberos. That's okay, just add to the file). We will add to this file, the following snippet:

```
Server {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  keyTab="conf/zookeeper-server.keytab"
  storeKey=true
  useTicketCache=false
  principal="zookeeper/myHost.example.com@EXAMPLE.COM" ;
};
```

Be sure to replace the value of *principal* above with the appropriate Principal, including the fully qualified domain name of the server.

Next, we need to tell NiFi to use this as our JAAS configuration. This is done by setting a JVM System Property, so we will edit the `conf/bootstrap.conf` file. If the Client has already been configured to use Kerberos, this is not necessary, as it was done above. Otherwise, we will add the following line to our `bootstrap.conf` file:

```
java.arg.15=-Djava.security.auth.login.config=./conf/zookeeper-jaas.conf
```

Note: this additional line in the file doesn't have to be number 15, it just has to be added to the `bootstrap.conf` file, use whatever number is appropriate for your configuration.

We will want to initialize our Kerberos ticket by running the following command:

```
kinit -kt zookeeper-server.keytab "zookeeper/myHost.example.com@EXAMPLE.COM"
```

Again, be sure to replace the Principal with the appropriate value, including your realm and your fully qualified hostname.

Finally, we need to tell the Kerberos server to use the SASL Authentication Provider. To do this, we edit the `$NIFI_HOME/conf/zookeeper.properties` file and add the following lines:

```
authProvider.1=org.apache.zookeeper.server.auth.SASLAuthenticationProvider
kerberos.removeHostFromPrincipal=true
kerberos.removeRealmFromPrincipal=true
jaasLoginRenew=3600000
requireClientAuthScheme=sasl
```

The `kerberos.removeHostFromPrincipal` and the `kerberos.removeRealmFromPrincipal` properties are used to normalize the user principal name before comparing an identity to acls applied on a Znode. By default the full principal is used however setting the `removeHostFromPrincipal` and `removeRealmFromPrincipal` kerberos properties to true will instruct ZooKeeper to remove the host and the realm from the logged in user's identity for comparison. In cases where NiFi nodes (within the same cluster) use principals that have different host(s)/realm(s) values, these kerberos properties can be configured to ensure

that the nodes' identity will be normalized and that the nodes will have appropriate access to shared Znodes in ZooKeeper.

The last line is optional but specifies that clients **MUST** use Kerberos to communicate with our ZooKeeper instance.

Now, we can start NiFi, and the embedded ZooKeeper server will use Kerberos as the authentication mechanism.

1.1.9.4.2. Kerberizing NiFi's ZooKeeper Client

Note: The NiFi nodes running the embedded zookeeper server will also need to follow the below procedure since they will also be acting as a client at the same time.

The preferred mechanism for authenticating users with ZooKeeper is to use Kerberos. In order to use Kerberos to authenticate, we must configure a few system properties, so that the ZooKeeper client knows who the user is and where the KeyTab file is. All nodes configured to store cluster-wide state using `ZooKeeperStateProvider` and using Kerberos should follow these steps.

First, we must create the Principal that we will use when communicating with ZooKeeper. This is generally done via the `kadmin` tool:

```
kadmin: addprinc "nifi@EXAMPLE.COM"
```

A Kerberos Principal is made up of three parts: the primary, the instance, and the realm. Here, we are creating a Principal with the primary `nifi`, no instance, and the realm `EXAMPLE.COM`. The primary (`nifi`, in this case) is the identifier that will be used to identify the user when authenticating via Kerberos.

After we have created our Principal, we will need to create a KeyTab for the Principal:

```
kadmin: xst -k nifi.keytab nifi@EXAMPLE.COM
```

This keytab file can be copied to the other NiFi nodes with embedded zookeeper servers.

This will create a file in the current directory named `nifi.keytab`. We can now copy that file into the `$NIFI_HOME/conf/` directory. We should ensure that only the user that will be running NiFi is allowed to read this file.

Next, we need to configure NiFi to use this KeyTab for authentication. Since ZooKeeper uses the Java Authentication and Authorization Service (JAAS), we need to create a JAAS-compatible file. In the `$NIFI_HOME/conf/` directory, create a file named `zookeeper-jaas.conf` and add to it the following snippet:

```
Client {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  keyTab="conf/nifi.keytab"
  storeKey=true
  useTicketCache=false
  principal="nifi@EXAMPLE.COM" ;
};
```

We then need to tell NiFi to use this as our JAAS configuration. This is done by setting a JVM System Property, so we will edit the `conf/bootstrap.conf` file. We add the following line anywhere in this file in order to tell the NiFi JVM to use this configuration:

```
java.arg.15=-Djava.security.auth.login.config=./conf/zookeeper-jaas.conf
```

Finally we need to update `nifi.properties` to ensure that NiFi knows to apply SASL specific ACLs for the Znodes it will create in ZooKeeper for cluster management. To enable this, in the `$NIFI_HOME/conf/nifi.properties` file and edit the following properties as shown below:

```
nifi.zookeeper.auth.type=sasl
nifi.zookeeper.kerberos.removeHostFromPrincipal=true
nifi.zookeeper.kerberos.removeRealmFromPrincipal=true
```

Note: The `kerberos.removeHostFromPrincipal` and `kerberos.removeRealmFromPrincipal` should be consistent with what is set in ZooKeeper configuration.

We can initialize our Kerberos ticket by running the following command:

```
kinit -kt nifi.keytab nifi@EXAMPLE.COM
```

Now, when we start NiFi, it will use Kerberos to authentication as the `nifi` user when communicating with ZooKeeper.

1.1.9.4.3. Troubleshooting Kerberos Configuration

When using Kerberos, it is import to use fully-qualified domain names and not use `localhost`. Please ensure that the fully qualified hostname of each server is used in the following locations:

- `conf/zookeeper.properties` file should use FQDN for `server.1`, `server.2`, ..., `server.N` values.
- The `Connect String` property of the `ZooKeeperStateProvider`
- The `/etc/hosts` file should also resolve the FQDN to an IP address that is **not** `127.0.0.1`.

Failure to do so, may result in errors similar to the following:

```
2016-01-08 16:08:57,888 ERROR [pool-26-thread-1-SendThread(localhost:2181)]
o.a.zookeeper.client.ZooKeeperSaslClient An error: (java.security.
PrivilegedActionException: javax.security.sasl.SaslException: GSS initiate
failed [Caused by GSSException: No valid credentials provided (Mechanism
level: Server not found in Kerberos database (7) - LOOKING_UP_SERVER)])
occurred when evaluating ZooKeeper Quorum Member's received SASL token.
ZooKeeper Client will go to AUTH_FAILED state.
```

If there are problems communicating or authenticating with Kerberos, [this Troubleshooting Guide](#) may be of value.

One of the most important notes in the above Troubleshooting guide is the mechanism for turning on Debug output for Kerberos. This is done by setting the `sun.security.krb5.debug` environment variable. In NiFi, this is accomplished by adding the following line to the `_$NIFI_HOME/conf/bootstrap.conf`` file:

```
java.arg.16=-Dsun.security.krb5.debug=true
```

This will cause the debug output to be written to the NiFi Bootstrap log file. By default, this is located at `$NIFI_HOME/logs/nifi-bootstrap.log`. This output can be rather verbose but provides extremely valuable information for troubleshooting Kerberos failures.

1.1.9.5. ZooKeeper Migrator

You can use the NiFi ZooKeeper Migrator to perform the following tasks:

- Moving ZooKeeper information from one ZooKeeper cluster to another
- Migrating ZooKeeper node ownership

For example, you may want to use the ZooKeeper Migrator when you are:

- Upgrading from NiFi 0.x to NiFi 1.x in which embedded ZooKeepers are used
- Migrating from an embedded ZooKeeper in NiFi 0.x or 1.x to an external ZooKeeper
- Upgrading from NiFi 0.x with an external ZooKeeper to NiFi 1.x with the same external ZooKeeper
- Migrating from an external ZooKeeper to an embedded ZooKeeper in NiFi 1.x

The NiFi ZooKeeper Migrator is part of the NiFi Toolkit and is downloaded separately from the [Apache NiFi download page](#).

1.1.9.5.1. zk-migrator.sh Command Line Parameters

You can use the following command line options with the ZooKeeper Migrator:

- `-a,--auth <username:password>` Allows the specification of a username and password for authentication with ZooKeeper. This option is mutually exclusive with the `-k,--krb-conf` option.
- `-f,--file <filename>` The file used for ZooKeeper data serialized as JSON. When used with the `-r,--receive` option, data read from ZooKeeper will be stored in the given filename. When used with the `-s,--send` option, the data in the file will be sent to ZooKeeper.
- `-h,--help` Prints help, displays available parameters with descriptions
- `--ignore-source` Allows the ZooKeeper Migrator to write to the ZooKeeper and path from which the data was obtained.
- `-k,--krb-conf <jaas-filename>` Allows the specification of a JAAS configuration file to allow authentication with a ZooKeeper configured to use Kerberos. This option is mutually exclusive with the `-a,--auth` option.
- `-r,--receive` Receives data from ZooKeeper and writes to the given filename (if the `-f,--file` option is provided) or standard output. The data received will contain the full path to each node read from ZooKeeper. This option is mutually exclusive with the `-s,--send` option.
- `-s,--send` Sends data to ZooKeeper that is read from the given filename (if the `-f,--file` option is provided) or standard input. The paths for each node in the data being sent to ZooKeeper are absolute paths, and will be stored in ZooKeeper under the **path** portion of the `-z,--zookeeper` argument. Typically, the **path** portion of the argument

can be omitted, which will store the nodes at their absolute paths. This option is mutually exclusive with the `-r,--receive` option.

- `--use-existing-acl` Allows the ZooKeeper Migrator to write ACL values retrieved from the source ZooKeeper server to destination server. Default action will apply Open rights for unsecured destinations or Creator Only rights for secured destinations.
- `-z,--zookeeper <zookeeper-endpoint>` The ZooKeeper server(s) to use, specified by a connect string, comprised of one or more comma-separated host:port pairs followed by a path, in the format of `host:port[,host2:port...,hostn:port]/znode/path`.

1.1.9.5.2. Migrating Between Source and Destination ZooKeepers

Before you begin, confirm that:

- You have installed the destination ZooKeeper cluster.
- You have installed and configured a NiFi cluster to use the destination ZooKeeper cluster.
- If you are migrating ZooKeepers due to upgrading NiFi from 0.x to 1.x,, you have already followed appropriate NiFi upgrade steps.
- You have configured Kerberos as needed.
- You have not started processing any dataflow (to avoid duplicate data processing).
- If one of the ZooKeeper clusters you are using is configured with Kerberos, you are running the ZooKeeper Migrator from a host that has access to NiFi's ZooKeeper client jaas configuration file (see [Kerberizing NiFi's ZooKeeper Client](#) for more information).

1.1.9.5.2.1. ZooKeeper Migration Steps

1. Collect the following information:

Required Information	Description
Source ZooKeeper hostname (sourceHostname)	The hostname must be one of the hosts running in the ZooKeeper ensemble, which can be found in <code><NiFi installation dir>/conf/zookeeper.properties</code> . Any of the hostnames declared in the <code>server.N</code> properties can be used.
Destination ZooKeeper hostname (destinationHostname)	The hostname must be one of the hosts running in the ZooKeeper ensemble, which can be found in <code><NiFi installation dir>/conf/zookeeper.properties</code> . Any of the hostnames declared in the <code>server.N</code> properties can be used.
Source ZooKeeper port (sourceClientPort)	This can be found in <code>zookeeper.properties</code> of the <code><NiFi installation dir>/conf/zookeeper.properties</code> . The port is specified in the <code>clientPort</code> property.
Destination ZooKeeper port (destinationClientPort)	This can be found in <code>zookeeper.properties</code> of the <code><NiFi installation dir>/conf/zookeeper.properties</code> . The port is specified in the <code>clientPort</code> property.
Export data path	Determine the path that will store a json file containing the export of data from ZooKeeper. It must be readable and writable by the user running the <code>zk-migrator</code> tool.
Source ZooKeeper Authentication Information	This information is in <code><NiFi installation dir>/conf/state-management.xml</code> . For NiFi 0.x, if Creator Only is specified in <code>state-management.xml</code> , you need to

	supply authentication information using the <code>-a, --auth</code> argument with the values from the Username and Password properties in <code>state-management.xml</code> . For NiFi 1.x, supply authentication information using the <code>-k, --krb-conf</code> argument. + If the <code>state-management.xml</code> specifies <code>Open</code> , no authentication is required.
Destination ZooKeeper Authentication Information	This information is in <code><NiFi installation dir>/conf/state-management.xml</code> . For NiFi 0.x, if <code>Creator Only</code> is specified in <code>state-management.xml</code> , you need to supply authentication information using the <code>-a, --auth</code> argument with the values from the Username and Password properties in <code>state-management.xml</code> . For NiFi 1.x, supply authentication information using the <code>-k, --krb-conf</code> argument. + If the <code>state-management.xml</code> specifies <code>Open</code> , no authentication is required.
Root path to which NiFi writes data in Source ZooKeeper (<code>sourceRootPath</code>)	This information can be found in <code><NiFi installation dir>/conf/state-management.xml</code> under the <code>Root Node</code> property in the <code>cluster-provider</code> element. (default: <code>/nifi</code>)
Root path to which NiFi writes data in Destination ZooKeeper (<code>destinationRootPath</code>)	This information can be found in <code><NiFi installation dir>/conf/state-management.xml</code> under the <code>Root Node</code> property in the <code>cluster-provider</code> element.

2. Stop all processors in the NiFi flow. If you are migrating between two NiFi installations, the flows on both must be stopped.
3. Export the NiFi component data from the source ZooKeeper. The following command reads from the specified ZooKeeper running on the given `hostname:port`, using the provided path to the data, and authenticates with ZooKeeper using the given username and password. The data read from ZooKeeper is written to the file provided.
 - For NiFi 0.x
 - For an open ZooKeeper:
 - `zk-migrator.sh -r -z sourceHostname:sourceClientPort/sourceRootPath/components -f /path/to/export/zk-source-data.json`
 - For a ZooKeeper using `username:password` for authentication:
 - `zk-migrator.sh -r -z sourceHostname:sourceClientPort/sourceRootPath/components -a <username:password> -f /path/to/export/zk-source-data.json`
 - For NiFi 1.x
 - For an open ZooKeeper:
 - `zk-migrator.sh -r -z sourceHostname:sourceClientPort/sourceRootPath/components -f /path/to/export/zk-source-data.json`
 - For a ZooKeeper using Kerberos for authentication:
 - `zk-migrator.sh -r -z sourceHostname:sourceClientPort/sourceRootPath/components -k /path/to/jaasconfig/jaas-config.conf -f /path/to/export/zk-source-data.json`
4. (Optional) If you have used the new NiFi installation to do any processing, you can also export its ZooKeeper data as a backup prior to performing the migration.

- For an open ZooKeeper:
 - `zk-migrator.sh -r -z destinationHostname:destinationClientPort/destinationRootPath/components -f /path/to/export/zk-destination-backup-data.json`
 - For a ZooKeeper using Kerberos for authentication:
 - `zk-migrator.sh -r -z destinationHostname:destinationClientPort/destinationRootPath/components -k /path/to/jaasconfig/jaas-config.conf -f /path/to/export/zk-destination-backup-data.json`
5. Migrate the ZooKeeper data to the destination ZooKeeper. If the source and destination ZooKeepers are the same, the `--ignore-source` option can be added to the following examples.
- For an open ZooKeeper:
 - `zk-migrator.sh -s -z destinationHostname:destinationClientPort/destinationRootPath/components -f /path/to/export/zk-source-data.json`
 - For a ZooKeeper using Kerberos for authentication:
 - `zk-migrator.sh -s -z destinationHostname:destinationClientPort/destinationRootPath/components -k /path/to/jaasconfig/jaas-config.conf -f /path/to/export/zk-source-data.json`
6. Once the migration has completed successfully, start the processors in the NiFi flow. Processing should continue from the point at which it was stopped when the NiFi flow was stopped.

1.1.10. Bootstrap Properties

The *bootstrap.conf* file in the *conf* directory allows users to configure settings for how NiFi should be started. This includes parameters, such as the size of the Java Heap, what Java command to run, and Java System Properties.

Here, we will address the different properties that are made available in the file. Any changes to this file will take effect only after NiFi has been stopped and restarted.

Property	Description
java	Specifies the fully qualified java command to run. By default, it is simply <code>java</code> but could be changed to an absolute path or a reference an environment variable, such as <code>\$JAVA_HOME/bin/java</code>
run.as	The username to run NiFi as. For instance, if NiFi should be run as the 'nifi' user, setting this value to 'nifi' will cause the NiFi Process to be run as the 'nifi' user. This property is ignored on Windows. For Linux, the specified user may require <code>sudo</code> permissions.
lib.dir	The <i>lib</i> directory to use for NiFi. By default, this is set to <code>./lib</code>

conf.dir	The <i>conf</i> directory to use for NiFi. By default, this is set to <code>./conf</code>
graceful.shutdown.seconds	When NiFi is instructed to shutdown, the Bootstrap will wait this number of seconds for the process to shutdown cleanly. At this amount of time, if the service is still running, the Bootstrap will "kill" the process, or terminate it abruptly.
java.arg.N	Any number of JVM arguments can be passed to the NiFi JVM when the process is started. These arguments are defined by adding properties to <i>bootstrap.conf</i> that begin with <code>java.arg.</code> . The rest of the property name is not relevant, other than to different property names, and will be ignored. The default includes properties for minimum and maximum Java Heap size, the garbage collector to use, etc.
notification.services.file	When NiFi is started, or stopped, or when the Bootstrap detects that NiFi has died, the Bootstrap is able to send notifications of these events to interested parties. This is configured by specifying an XML file that defines which notification services can be used. More about this file can be found in the Notification Services section.
notification.max.attempts	If a notification service is configured but is unable to perform its function, it will try again up to a maximum number of attempts. This property configures what that maximum number of attempts is. The default value is 5.
nifi.start.notification.services	This property is a comma-separated list of Notification Service identifiers that correspond to the Notification Services defined in the <code>notification.services.file</code> property. The services with the specified identifiers will be used to notify their configured recipients whenever NiFi is started.
nifi.stop.notification.services	This property is a comma-separated list of Notification Service identifiers that correspond to the Notification Services defined in the <code>notification.services.file</code> property. The services with the specified identifiers will be used to notify their configured recipients whenever NiFi is stopped.
nifi.died.notification.services	This property is a comma-separated list of Notification Service identifiers that correspond to the Notification Services defined in the <code>notification.services.file</code> property. The services with the specified identifiers will be used to notify their configured recipients if the bootstrap determines that NiFi has unexpectedly died.

1.1.11. Notification Services

When the NiFi bootstrap starts or stops NiFi, or detects that it has died unexpectedly, it is able to notify configured recipients. Currently, the only mechanisms supplied are to send an e-mail or HTTP POST notification. The notification services configuration file is an XML file where the notification capabilities are configured.

The default location of the XML file is `conf/bootstrap-notification-services.xml`, but this value can be changed in the `conf/bootstrap.conf` file.

The syntax of the XML file is as follows:

```
<services>
  <!-- any number of service elements can be defined. -->
  <service>
    <id>some-identifier</id>
```



```

<!-- The fully-qualified class name of the Notification Service. -->
<class>org.apache.nifi.bootstrap.notification.email.
EmailNotificationService</class>

<!-- Any number of properties can be set using this syntax.
      The properties available depend on the Notification Service. -->
<property name="Property Name 1">Property Value</property>
<property name="Another Property Name">Property Value 2</property>
</service>
</services>

```

Once the desired services have been configured, they can then be referenced in the *bootstrap.conf* file.

1.1.11.1. Email Notification Service

The first Notifier is to send emails and the implementation is `org.apache.nifi.bootstrap.notification.email.EmailNotificationService`. It has the following properties available:

Property	Required	Description
SMTP Hostname	true	The hostname of the SMTP Server that is used to send Email Notifications
SMTP Port	true	The Port used for SMTP communications
SMTP Username	true	Username for the SMTP account
SMTP Password		Password for the SMTP account
SMTP Auth		Flag indicating whether authentication should be used
SMTP TLS		Flag indicating whether TLS should be enabled
SMTP Socket Factory		<code>javax.net.ssl.SSLSocketFactory</code>
SMTP X-Mailer Header		X-Mailer used in the header of the outgoing email
Content Type		Mime Type used to interpret the contents of the email, such as <code>text/plain</code> or <code>text/html</code>
From	true	Specifies the Email address to use as the sender. Otherwise, a "friendly name" can be used as the From address, but the value must be enclosed in double-quotes.
To		The recipients to include in the To-Line of the email
CC		The recipients to include in the CC-Line of the email
BCC		The recipients to include in the BCC-Line of the email

In addition to the properties above that are marked as required, at least one of the `To`, `CC`, or `BCC` properties must be set.

A complete example of configuring the Email service would look like the following:

```
<service>
```

```

<id>email-notification</id>
<class>org.apache.nifi.bootstrap.notification.email.
EmailNotificationService</class>
<property name="SMTP Hostname">smtp.gmail.com</property>
<property name="SMTP Port">587</property>
<property name="SMTP Username">username@gmail.com</property>
<property name="SMTP Password">super-secret-password</property>
<property name="SMTP TLS">true</property>
<property name="From">"NiFi Service Notifier"</property>
<property name="To">username@gmail.com</property>
</service>

```

1.1.11.2. HTTP Notification Service

The second Notifier is to send HTTP POST requests and the implementation is `org.apache.nifi.bootstrap.notification.http.HttpNotificationService`. It has the following properties available:

Property	Required	Description
URL	true	The URL to send the notification to. Expression language is supported.
Connection timeout		Max wait time for connection to remote service. Expression language is supported. This defaults to 10s.
Write timeout		Max wait time for remote service to read the request sent. Expression language is supported. This defaults to 10s.
Truststore Filename		The fully-qualified filename of the Truststore
Truststore Type		The Type of the Truststore. Either JKS or PKCS12
Truststore Password		The password for the Truststore
Keystore Filename		The fully-qualified filename of the Keystore
Keystore Type		The password for the Keystore
Keystore Password		The password for the key. If this is not specified, but the Keystore Filename, Password, and Type are specified, then the Keystore Password will be assumed to be the same as the Key Password.
SSL Protocol		The algorithm to use for this SSL context. This can either be "SSL" or "TLS".

In addition to the properties above, dynamic properties can be added. They will be added as headers to the HTTP request. Expression language is supported.

The notification message is in the body of the POST request. The type of notification is in the header "notification.type" and the subject uses the header "notification.subject".

A complete example of configuring the HTTP service could look like the following:

```

<service>
  <id>http-notification</id>
  <class>org.apache.nifi.bootstrap.notification.http.
HttpNotificationService</class>

```

```

<property name="URL">https://testServer.com:8080/</property>
<property name="Truststore Filename">localhost-ts.jks</property>
<property name="Truststore Type">JKS</property>
<property name="Truststore Password">localtest</property>
<property name="Keystore Filename">localhost-ts.jks</property>
<property name="Keystore Type">JKS</property>
<property name="Keystore Password">localtest</property>
<property name="notification.timestamp">${now()}</property>
</service>

```

1.1.12. Proxy Configuration

When running Apache NiFi behind a proxy there are a couple of key items to be aware of during deployment.

- NiFi is comprised of a number of web applications (web UI, web API, documentation, custom UIs, data viewers, etc), so the mapping needs to be configured for the **root path**. That way all context paths are passed through accordingly. For instance, if only the `/nifi` context path was mapped, the custom UI for `UpdateAttribute` will not work, since it is available at `/update-attribute-ui-<version>`.
- NiFi's REST API will generate URIs for each component on the graph. Since requests are coming through a proxy, certain elements of the URIs being generated need to be overridden. Without overriding, the users will be able to view the dataflow on the canvas but will be unable to modify existing components. Requests will be attempting to call back directly to NiFi, not through the proxy. The elements of the URI can be overridden by adding the following HTTP headers when the proxy generates the HTTP request to the NiFi instance:

```

X-ProxyScheme - the scheme to use to connect to the proxy
X-ProxyHost - the host of the proxy
X-ProxyPort - the port the proxy is listening on
X-ProxyContextPath - the path configured to map to the NiFi instance

```

- If NiFi is running securely, any proxy needs to be authorized to proxy user requests. These can be configured in the NiFi UI through the Global Menu. Once these permissions are in place, proxies can begin proxying user requests. The end user identity must be relayed in a HTTP header. For example, if the end user sent a request to the proxy, the proxy must authenticate the user. Following this the proxy can send the request to NiFi. In this request an HTTP header should be added as follows.

```
X-ProxiedEntitiesChain: <end-user-identity>
```

If the proxy is configured to send to another proxy, the request to NiFi from the second proxy should contain a header as follows.

```
X-ProxiedEntitiesChain: <end-user-identity><proxy-1-identity>
```

An example Apache proxy configuration that sets the required properties may look like the following. Complete proxy configuration is outside of the scope of this document. Please refer the documentation of the proxy for guidance for your deployment environment and use case.

```
...
```

```

<Location "/my-nifi">
  ...
  SSLEngine On
  SSLCertificateFile /path/to/proxy/certificate.crt
  SSLCertificateKeyFile /path/to/proxy/key.key
  SSLCertificateFile /path/to/ca/certificate.crt
  SSLVerifyClient require
  RequestHeader add X-ProxyScheme "https"
  RequestHeader add X-ProxyHost "proxy-host"
  RequestHeader add X-ProxyPort "443"
  RequestHeader add X-ProxyContextPath "/my-nifi"
  RequestHeader add X-ProxiedEntitiesChain "<%{SSL_CLIENT_S_DN}>"
  ProxyPass https://nifi-host:8443
  ProxyPassReverse https://nifi-host:8443
  ...
</Location>
...

```

1.1.13. Kerberos Service

NiFi can be configured to use Kerberos SPNEGO (or "Kerberos Service") for authentication. In this scenario, users will hit the REST endpoint `/access/kerberos` and the server will respond with a 401 status code and the challenge response header `WWW-Authenticate: Negotiate`. This communicates to the browser to use the GSS-API and load the user's Kerberos ticket and provide it as a Base64-encoded header value in the subsequent request. It will be of the form `Authorization: Negotiate YII....` NiFi will attempt to validate this ticket with the KDC. If it is successful, the user's *principal* will be returned as the identity, and the flow will follow login/credential authentication, in that a JWT will be issued in the response to prevent the unnecessary overhead of Kerberos authentication on every subsequent request. If the ticket cannot be validated, it will return with the appropriate error response code. The user will then be able to provide their Kerberos credentials to the login form if the `KerberosLoginIdentityProvider` has been configured. See [Kerberos login identity provider](#) for more details.

NiFi will only respond to Kerberos SPNEGO negotiation over an HTTPS connection, as unsecured requests are never authenticated.

The following properties must be set in `nifi.properties` to enable Kerberos service authentication.

Property	Required	Description
Service Principal	true	The service principal used by NiFi to communicate with the KDC
Keytab Location	true	The file path to the keytab containing the service principal

See [Kerberos Properties](#) for complete documentation.

1.1.13.1. Notes

- Kerberos is case-sensitive in many places and the error messages (or lack thereof) may not be sufficiently explanatory. Check the case sensitivity of the service principal in your configuration files. Convention is `HTTP/fully.qualified.domain@REALM`.

- Browsers have varying levels of restriction when dealing with SPNEGO negotiations. Some will provide the local Kerberos ticket to any domain that requests it, while others whitelist the trusted domains. See [Spring Security Kerberos - Reference Documentation: Appendix E. Configure browsers for SPNEGO Negotiation](#) for common browsers.
- Some browsers (legacy IE) do not support recent encryption algorithms such as AES, and are restricted to legacy algorithms (DES). This should be noted when generating keytabs.
- The KDC must be configured and a service principal defined for NiFi and a keytab exported. Comprehensive instructions for Kerberos server configuration and administration are beyond the scope of this document (see [MIT Kerberos Admin Guide](#)), but an example is below:

Adding a service principal for a server at `nifi.nifi.apache.org` and exporting the keytab from the KDC:

```
root@kdc:/etc/krb5kdc# kadmin.local
Authenticating as principal admin/admin@NIFI.APACHE.ORG with password.
kadmin.local: listprincs
K/M@NIFI.APACHE.ORG
admin/admin@NIFI.APACHE.ORG
...
kadmin.local: addprinc -randkey HTTP/nifi.nifi.apache.org
WARNING: no policy specified for HTTP/nifi.nifi.apache.org@NIFI.APACHE.ORG;
defaulting to no policy
Principal "HTTP/nifi.nifi.apache.org@NIFI.APACHE.ORG" created.
kadmin.local: ktadd -k /http-nifi.keytab HTTP/nifi.nifi.apache.org
Entry for principal HTTP/nifi.nifi.apache.org with kvno 2, encryption type
des3-cbc-shal added to keytab WRFILE:/http-nifi.keytab.
Entry for principal HTTP/nifi.nifi.apache.org with kvno 2, encryption type
des-cbc-crc added to keytab WRFILE:/http-nifi.keytab.
kadmin.local: listprincs
HTTP/nifi.nifi.apache.org@NIFI.APACHE.ORG
K/M@NIFI.APACHE.ORG
admin/admin@NIFI.APACHE.ORG
...
kadmin.local: q
root@kdc:~# ll /http*
-rw----- 1 root root 162 Mar 14 21:43 /http-nifi.keytab
root@kdc:~#
```

1.1.14. System Properties

The *nifi.properties* file in the *conf* directory is the main configuration file for controlling how NiFi runs. This section provides an overview of the properties in this file and includes some notes on how to configure it in a way that will make upgrading easier. **After making changes to this file, restart NiFi in order for the changes to take effect.**

The contents of this file are relatively stable but do change from time to time. It is always a good idea to review this file when upgrading and pay attention for any changes. Consider configuring items below marked with an asterisk (*) in such a way that upgrading will be easier. For details, see a full discussion on upgrading at the end of this section. Note that values for periods of time and data sizes must include the unit of measure, for example "10 secs" or "10 MB", not simply "10".

1.1.14.1. Core Properties

The first section of the *nifi.properties* file is for the Core Properties. These properties apply to the core framework as a whole.

Property	Description
<code>nifi.flow.configuration.file*</code>	The location of the flow configuration file (i.e., the file that contains what is currently displayed on the NiFi graph). The default value is <code>./conf/flow.xml.gz</code> .
<code>nifi.flow.configuration.archive.enabled*</code>	Specifies whether NiFi creates a backup copy of the flow automatically when the flow is updated. The default value is <code>true</code> .
<code>nifi.flow.configuration.archive.dir*</code>	<p>The location of the archive directory where backup copies of the flow.xml are saved. The default value is <code>./conf/archive</code>. NiFi removes old archive files to limit disk usage based on archived file lifespan, total size, and number of files, as specified with <code>nifi.flow.configuration.archive.max.time</code>, <code>max.storage</code> and <code>max.count</code> properties respectively. If none of these limitation for archiving is specified, NiFi uses default condition, that is "30 days" for <code>max.time</code> and "500 MB" for <code>max.storage</code>.</p> <p>This cleanup mechanism takes into account only automatically created archived flow.xml files. If there are other files or directories in this archive directory, NiFi will ignore them. Automatically created archives have filename with ISO 8601 format timestamp prefix followed by '<i><original-filename></i>'. That is <code><year><month><day>T<hour><minute><second>+<timezone offset><original filename></code>. For example, <code>20160706T160719+0900_flow.xml.gz</code>. NiFi checks filenames when it cleans archive directory. If you would like to keep a particular archive in this directory without worrying about NiFi deleting it, you can do so by copying it with a different filename pattern.</p>
<code>nifi.flow.configuration.archive.max.time*</code>	The lifespan of archived flow.xml files. NiFi will delete expired archive files when it updates flow.xml if this property is specified. Expiration is determined based on current system time and the last modified timestamp of an archived flow.xml. If no archive limitation is specified in <i>nifi.properties</i> , NiFi removes archives older than "30 days".
<code>nifi.flow.configuration.archive.max.storage*</code>	The total data size allowed for the archived flow.xml files. NiFi will delete the oldest archive files until the total archived file size becomes less than this configuration value, if this property is specified. If no archive limitation is specified in <i>nifi.properties</i> , NiFi uses "500 MB" for this.
<code>nifi.flow.configuration.archive.max.count*</code>	The number of archive files allowed. NiFi will delete the oldest archive files so that only N latest archives can be kept, if this property is specified.
<code>nifi.flowcontroller.autoResumeState</code>	Indicates whether -upon restart- the components on the NiFi graph should return to their last state. The default value is <code>true</code> .
<code>nifi.flowcontroller.graceful.shutdown.period</code>	Indicates the shutdown period. The default value is 10 secs.
<code>nifi.flowservice.writedelay.interval</code>	When many changes are made to the flow.xml, this property specifies how long to wait before writing out the changes, so as to batch the changes into a single write. The default value is 500 ms.
<code>nifi.administrative.yield.duration</code>	If a component allows an unexpected exception to escape, it is considered a bug. As a result, the framework will

	pause (or administratively yield) the component for this amount of time. This is done so that the component does not use up massive amounts of system resources, since it is known to have problems in the existing state. The default value is 30 secs.
nifi.bored.yield.duration	When a component has no work to do (i.e., is "bored"), this is the amount of time it will wait before checking to see if it has new data to work on. This way, it does not use up CPU resources by checking for new work too often. When setting this property, be aware that it could add extra latency for components that do not constantly have work to do, as once they go into this "bored" state, they will wait this amount of time before checking for more work. The default value is 10 ms.
nifi.authorizer.configuration.file*	This is the location of the file that specifies how authorizers are defined. The default value is <code>./conf/authorizers.xml</code> .
nifi.login.identity.provider.configuration.file*	This is the location of the file that specifies how username/password authentication is performed. This file is only considered if <code>nifi.security.user.login.identity.provider</code> is configured with a provider identifier. The default value is <code>./conf/login-identity-providers.xml</code> .
nifi.templates.directory*	This is the location of the directory where flow templates are saved (for backward compatibility only). Templates are stored in the <code>flow.xml.gz</code> starting with NiFi 1.0. The template directory can be used to (bulk) import templates into the <code>flow.xml.gz</code> automatically on NiFi startup. The default value is <code>./conf/templates</code> .
nifi.ui.banner.text	This is banner text that may be configured to display at the top of the User Interface. It is blank by default.
nifi.ui.autorefresh.interval	The interval at which the User Interface auto-refreshes. The default value is 30 secs.
nifi.nar.library.directory	The location of the nar library. The default value is <code>./lib</code> and probably should be left as is. NOTE: Additional library directories can be specified by using the <code>nifi.nar.library.directory</code> prefix with unique suffixes and separate paths as values. For example, to provide two additional library locations, a user could also specify additional properties with keys of: <code>nifi.nar.library.directory.lib1=/nars/lib1</code> <code>nifi.nar.library.directory.lib2=/nars/lib2</code> Providing three total locations, including <code>nifi.nar.library.directory</code> .
nifi.nar.working.directory	The location of the nar working directory. The default value is <code>./work/nar</code> and probably should be left as is.
nifi.documentation.working.directory	The documentation working directory. The default value is <code>./work/docs/components</code> and probably should be left as is.
nifi.processor.scheduling.timeout	Time to wait for a Processor's life-cycle operation (<code>@OnScheduled</code> and <code>@OnUnscheduled</code>) to finish before other life-cycle operation (e.g., stop) could be invoked. The default value is 1 min.

1.1.14.2. State Management

The State Management section of the Properties file provides a mechanism for configuring local and cluster-wide mechanisms for components to persist state. See the [State Management](#) section for more information on how this is used.

Property	Description
nifi.state.management.configuration.file	The XML file that contains configuration for the local and cluster-wide State Providers. The default value is <code>./conf/state-management.xml</code> .
nifi.state.management.provider.local	The ID of the Local State Provider to use. This value must match the value of the <code>id</code> element of one of the <code>local-provider</code> elements in the <code>state-management.xml</code> file.
nifi.state.management.provider.cluster	The ID of the Cluster State Provider to use. This value must match the value of the <code>id</code> element of one of the <code>cluster-provider</code> elements in the <code>state-management.xml</code> file. This value is ignored if not clustered but is required for nodes in a cluster.
nifi.state.management.embedded.zookeeper.start	Specifies whether or not this instance of NiFi should start an embedded ZooKeeper Server. This is used in conjunction with the <code>ZooKeeperStateProvider</code> .
nifi.state.management.embedded.zookeeper.properties	Specifies a properties file that contains the configuration for the embedded ZooKeeper Server that is started (if the <code>nifi.state.management.embedded.zookeeper.start</code> property is set to <code>true</code>)

1.1.14.3. H2 Settings

The H2 Settings section defines the settings for the H2 database, which keeps track of user access and flow controller history.

Property	Description
nifi.database.directory	The location of the H2 database directory. The default value is <code>./database_repository</code> .
nifi.h2.url.append	This property specifies additional arguments to add to the connection string for the H2 database. The default value should be used and should not be changed. It is: <code>;LOCK_TIMEOUT=25000;WRITE_DELAY=0;AUTO_SERVER=FALSE.</code>

1.1.14.4. FlowFile Repository

The FlowFile repository keeps track of the attributes and current state of each FlowFile in the system. By default, this repository is installed in the same root installation directory as all the other repositories; however, it is advisable to configure it on a separate drive if available.

Property	Description
nifi.flowfile.repository.implementation	The FlowFile Repository implementation. The default value is <code>org.apache.nifi.controller.repository.WriteAheadFlowFileRepository</code> and should only be changed with caution. To store flowfiles in memory instead of on disk (at the risk of data loss in the event of power/machine failure), set this property to <code>org.apache.nifi.controller.repository.VolatileFlowFileRepository</code> .
nifi.flowfile.repository.directory*	The location of the FlowFile Repository. The default value is <code>./flowfile_repository</code> .
nifi.flowfile.repository.partitions	The number of partitions. The default value is 256.

nifi.flowfile.repository.checkpoint.interval	The FlowFile Repository checkpoint interval. The default value is 2 mins.
nifi.flowfile.repository.always.sync	If set to <code>true</code> , any change to the repository will be synchronized to the disk, meaning that NiFi will ask the operating system not to cache the information. This is very expensive and can significantly reduce NiFi performance. However, if it is <code>false</code> , there could be the potential for data loss if either there is a sudden power loss or the operating system crashes. The default value is <code>false</code> .

1.1.14.5. Swap Management

NiFi keeps FlowFile information in memory (the JVM) but during surges of incoming data, the FlowFile information can start to take up so much of the JVM that system performance suffers. To counteract this effect, NiFi "swaps" the FlowFile information to disk temporarily until more JVM space becomes available again. These properties govern how that process occurs.

Property	Description
nifi.swap.manager.implementation	The Swap Manager implementation. The default value is <code>org.apache.nifi.controller.FileSystemSwapManager</code> and should not be changed.
nifi.queue.swap.threshold	The queue threshold at which NiFi starts to swap FlowFile information to disk. The default value is 20000.
nifi.swap.in.period	The swap in period. The default value is 5 sec.
nifi.swap.in.threads	The number of threads to use for swapping in. The default value is 1.
nifi.swap.out.period	The swap out period. The default value is 5 sec.
nifi.swap.out.threads	The number of threads to use for swapping out. The default value is 4.

1.1.14.6. Content Repository

The Content Repository holds the content for all the FlowFiles in the system. By default, it is installed in the same root installation directory as all the other repositories; however, administrators will likely want to configure it on a separate drive if available. If nothing else, it is best if the Content Repository is not on the same drive as the FlowFile Repository. In dataflows that handle a large amount of data, the Content Repository could fill up a disk and the FlowFile Repository, if also on that disk, could become corrupt. To avoid this situation, configure these repositories on different drives.

Property	Description
nifi.content.repository.implementation	The Content Repository implementation. The default value is <code>org.apache.nifi.controller.repository.FileSystemRepository</code> and should only be changed with caution. To store flowfile content in memory instead of on disk (at the risk of data loss in the event of power/machine failure), set this property to <code>org.apache.nifi.controller.repository.VolatileContentRepository</code> .

1.1.14.7. File System Content Repository Properties

Property	Description
nifi.content.repository.implementation	The Content Repository implementation. The default value is

	<p><code>org.apache.nifi.controller.repository.FileSystemRepository</code> and should only be changed with caution. To store flowfile content in memory instead of on disk (at the risk of data loss in the event of power/machine failure), set this property to <code>org.apache.nifi.controller.repository.VolatileContentRepository</code>.</p>
<code>nifi.content.claim.max.appendable.size</code>	The maximum size for a content claim. The default value is 10 MB.
<code>nifi.content.claim.max.flow.files</code>	The maximum number of FlowFiles to assign to one content claim. The default value is 100.
<code>nifi.content.repository.directory.default*</code>	<p>The location of the Content Repository. The default value is <code>./content_repository</code>.</p> <p>NOTE: Multiple content repositories can be specified by using the <code>nifi.content.repository.directory.</code> prefix with unique suffixes and separate paths as values.</p> <p>For example, to provide two additional locations to act as part of the content repository, a user could also specify additional properties with keys of:</p> <pre>nifi.content.repository.directory.content1=/repos/content1 nifi.content.repository.directory.content2=/repos/content2</pre> <p>Providing three total locations, including <code>nifi.content.repository.directory.default</code>.</p>
<code>nifi.content.repository.archive.max.retention.period</code>	If archiving is enabled (see <code>nifi.content.repository.archive.enabled</code> below), then this property specifies the maximum amount of time to keep the archived data. The default value is 12 hours.
<code>nifi.content.repository.archive.max.usage.percentage</code>	If archiving is enabled (see <code>nifi.content.repository.archive.enabled</code> below), then this property must have a value that indicates the content repository disk usage percentage at which archived data begins to be removed. If the archive is empty and content repository disk usage is above this percentage, then archiving is temporarily disabled. Archiving will resume when disk usage is below this percentage. The default value is 50%.
<code>nifi.content.repository.archive.enabled</code>	To enable content archiving, set this to <code>true</code> and specify a value for the <code>nifi.content.repository.archive.max.usage.percentage</code> property above. Content archiving enables the provenance UI to view or replay content that is no longer in a dataflow queue. By default, archiving is enabled.
<code>nifi.content.repository.always.sync</code>	If set to <code>true</code> , any change to the repository will be synchronized to the disk, meaning that NiFi will ask the operating system not to cache the information. This is very expensive and can significantly reduce NiFi performance. However, if it is <code>false</code> , there could be the potential for data loss if either there is a sudden power loss or the operating system crashes. The default value is <code>false</code> .
<code>nifi.content.viewer.url</code>	The URL for a web-based content viewer if one is available. It is blank by default.

1.1.14.8. Volatile Content Repository Properties

Property	Description
<code>nifi.volatile.content.repository.max.size</code>	The Content Repository maximum size in memory. The default value is 100 MB.

nifi.volatility.content.repository.block.size

The Content Repository block size. The default value is 32 KB.

1.1.14.9. Provenance Repository

The Provenance Repository contains the information related to Data Provenance. The next four sections are for Provenance Repository properties.

Property	Description
nifi.provenance.repository.implementation	<p>The Provenance Repository implementation. The default value is <code>org.apache.nifi.provenance.PersistentProvenanceRepository</code>. Two additional repositories are available as well. To store provenance events in memory instead of on disk (in which case all events will be lost on restart, and events will be evicted in a first-in-first-out order), set this property to <code>org.apache.nifi.provenance.VolatileProvenanceRepository</code>. This leaves a configurable number of Provenance Events in the Java heap, so the number of events that can be retained is very limited.</p> <p>As of Apache NiFi 1.2.0, a third and fourth option are available: <code>org.apache.nifi.provenance.WriteAheadProvenanceRepository</code> and <code>org.apache.nifi.provenance.EncryptedWriteAheadProvenanceRepository</code>. This implementation was created to replace the <code>PersistentProvenanceRepository</code>. The <code>PersistentProvenanceRepository</code> was originally written with the simple goal of persisting Provenance Events as they are generated and providing the ability to iterate over those events sequentially. Later, it was desired to be able to compress the data so that more data could be stored. After that, the ability to index and query the data was added. As requirements evolved over time, the repository kept changing without any major redesigns. When used in a NiFi instance that is responsible for processing large volumes of small FlowFiles, the <code>PersistentProvenanceRepository</code> can quickly become a bottleneck. The <code>WriteAheadProvenanceRepository</code> was then written to provide the same capabilities as the <code>PersistentProvenanceRepository</code> while providing far better performance. Changing to the <code>WriteAheadProvenanceRepository</code> is easy to accomplish, as the two repositories support most of the same properties.</p> <p>Note Well, however, the following caveat: The <code>WriteAheadProvenanceRepository</code> will make use of the Provenance data stored by the <code>PersistentProvenanceRepository</code>. However, the <code>PersistentProvenanceRepository</code> may not be able to read the data written by the <code>WriteAheadProvenanceRepository</code>. Therefore, once the Provenance Repository is changed to use the <code>WriteAheadProvenanceRepository</code>, it cannot be changed back to the <code>PersistentProvenanceRepository</code> without deleting the data in the Provenance Repository. It is therefore recommended that before changing the implementation, users ensure that their version of NiFi is stable, in case any issue arises that causes the user to need to roll back to a previous version of NiFi that did not support the <code>WriteAheadProvenanceRepository</code>.</p>

It is for this reason that the default is still set to the `PersistentProvenanceRepository` at this time.

1.1.14.10. Persistent Provenance Repository Properties

Property	Description
<code>nifi.provenance.repository.directory.default*</code>	<p>The location of the Provenance Repository. The default value is <code>./provenance_repository</code>.</p> <p>NOTE: Multiple provenance repositories can be specified by using the <code>nifi.provenance.repository.directory.</code> prefix with unique suffixes and separate paths as values.</p> <p>For example, to provide two additional locations to act as part of the provenance repository, a user could also specify additional properties with keys of:</p> <pre>nifi.provenance.repository.directory.provenance1=/repos/provenance1</pre> <pre>nifi.provenance.repository.directory.provenance2=/repos/provenance2</pre> <p>Providing three total locations, including <code>nifi.provenance.repository.directory.default</code>.</p>
<code>nifi.provenance.repository.max.storage.time</code>	The maximum amount of time to keep data provenance information. The default value is 24 hours.
<code>nifi.provenance.repository.max.storage.size</code>	The maximum amount of data provenance information to store at a time. The default value is 1 GB.
<code>nifi.provenance.repository.rollover.time</code>	The amount of time to wait before rolling over the latest data provenance information so that it is available in the User Interface. The default value is 30 secs.
<code>nifi.provenance.repository.rollover.size</code>	The amount of information to roll over at a time. The default value is 100 MB.
<code>nifi.provenance.repository.query.threads</code>	The number of threads to use for Provenance Repository queries. The default value is 2.
<code>nifi.provenance.repository.index.threads</code>	The number of threads to use for indexing Provenance events so that they are searchable. The default value is 2. For flows that operate on a very high number of FlowFiles, the indexing of Provenance events could become a bottleneck. If this is the case, a bulletin will appear, indicating that "The rate of the dataflow is exceeding the provenance recording rate. Slowing down flow to accommodate." If this happens, increasing the value of this property may increase the rate at which the Provenance Repository is able to process these records, resulting in better overall throughput.
<code>nifi.provenance.repository.compress.on.rollover</code>	Indicates whether to compress the provenance information when rolling it over. The default value is <code>true</code> .
<code>nifi.provenance.repository.always.sync</code>	If set to <code>true</code> , any change to the repository will be synchronized to the disk, meaning that NiFi will ask the operating system not to cache the information. This is very expensive and can significantly reduce NiFi performance. However, if it is <code>false</code> , there could be the potential for data loss if either there is a sudden power loss or the operating system crashes. The default value is <code>false</code> .
<code>nifi.provenance.repository.journal.count</code>	The number of journal files that should be used to serialize Provenance Event data. Increasing this value will allow more tasks to simultaneously update the repository but will result in more expensive merging of the journal files later. This value should ideally be equal to the number of threads that are expected to update the repository

	simultaneously, but 16 tends to work well in most environments. The default value is 16.
nifi.provenance.repository.indexed.fields	This is a comma-separated list of the fields that should be indexed and made searchable. Fields that are not indexed will not be searchable. Valid fields are: EventType, FlowFileUUID, Filename, TransiURI, ProcessorID, AlternateIdentifierURI, Relationship, Details. The default value is: EventType, FlowFileUUID, Filename, ProcessorID.
nifi.provenance.repository.indexed.attributes	This is a comma-separated list of FlowFile Attributes that should be indexed and made searchable. It is blank by default. But some good examples to consider are 'filename', 'uuid', and 'mime.type' as well as any custom attributes you might use which are valuable for your use case.
nifi.provenance.repository.index.shard.size	Large values for the shard size will result in more Java heap usage when searching the Provenance Repository but should provide better performance. The default value is 500 MB.
nifi.provenance.repository.max.attribute.length	Indicates the maximum length that a FlowFile attribute can be when retrieving a Provenance Event from the repository. If the length of any attribute exceeds this value, it will be truncated when the event is retrieved. The default value is 65536.

1.1.14.11. Volatile Provenance Repository Properties

Property	Description
nifi.provenance.repository.buffer.size	The Provenance Repository buffer size. The default value is 100000.

1.1.14.12. Write Ahead Provenance Repository Properties

Property	Description
nifi.provenance.repository.directory.default*	<p>The location of the Provenance Repository. The default value is <code>./provenance_repository</code>.</p> <p>NOTE: Multiple provenance repositories can be specified by using the <code>nifi.provenance.repository.directory.</code> prefix with unique suffixes and separate paths as values.</p> <p>For example, to provide two additional locations to act as part of the provenance repository, a user could also specify additional properties with keys of:</p> <pre>nifi.provenance.repository.directory.provenance1=/repos/provenance1</pre> <pre>nifi.provenance.repository.directory.provenance2=/repos/provenance2</pre> <p>Providing three total locations, including <code>nifi.provenance.repository.directory.default</code>.</p>
nifi.provenance.repository.max.storage.time	The maximum amount of time to keep data provenance information. The default value is 24 hours.
nifi.provenance.repository.max.storage.size	The maximum amount of data provenance information to store at a time. The default value is 1 GB. The Data Provenance capability can consume a great deal of storage space because so much data is kept. For production environments, values of 1-2 TB or more is not uncommon. The repository will write to a single "event file" (or set of "event files" if multiple storage locations are defined,

	as described above) for some period of time (defined by the <code>nifi.provenance.repository.rollover.time</code> and <code>nifi.provenance.repository.rollover.size</code> properties). Data is always aged off one file at a time, so it is not advisable to write to a single "event file" for a tremendous amount of time, as it will prevent old data from aging off as smoothly.
<code>nifi.provenance.repository.rollover.time</code>	The amount of time to wait before rolling over the "event file" that the repository is writing to.
<code>nifi.provenance.repository.rollover.size</code>	The amount of data to write to a single "event file." The default value is 100 MB. For production environments where a very large amount of Data Provenance is generated, a value of 1 GB is also very reasonable.
<code>nifi.provenance.repository.query.threads</code>	The number of threads to use for Provenance Repository queries. The default value is 2.
<code>nifi.provenance.repository.index.threads</code>	The number of threads to use for indexing Provenance events so that they are searchable. The default value is 2. For flows that operate on a very high number of FlowFiles, the indexing of Provenance events could become a bottleneck. If this happens, increasing the value of this property may increase the rate at which the Provenance Repository is able to process these records, resulting in better overall throughput. It is advisable to use at least 1 thread per storage location (i.e., if there are 3 storage locations, at least 3 threads should be used). For high throughput environments, where more CPU and disk I/O is available, it may make sense to increase this value significantly. Typically going beyond 2-4 threads per storage location is not valuable. However, this can be tuned depending on the CPU resources available compared to the I/O resources.
<code>nifi.provenance.repository.compress.on.rollover</code>	Indicates whether to compress the provenance information when an "event file" is rolled over. The default value is <code>true</code> .
<code>nifi.provenance.repository.always.sync</code>	If set to <code>true</code> , any change to the repository will be synchronized to the disk, meaning that NiFi will ask the operating system not to cache the information. This is very expensive and can significantly reduce NiFi performance. However, if it is <code>false</code> , there could be the potential for data loss if either there is a sudden power loss or the operating system crashes. The default value is <code>false</code> .
<code>nifi.provenance.repository.indexed.fields</code>	This is a comma-separated list of the fields that should be indexed and made searchable. Fields that are not indexed will not be searchable. Valid fields are: <code>EventType</code> , <code>FlowFileUUID</code> , <code>Filename</code> , <code>TransitURI</code> , <code>ProcessorID</code> , <code>AlternateIdentifierURI</code> , <code>Relationship</code> , <code>Details</code> . The default value is: <code>EventType</code> , <code>FlowFileUUID</code> , <code>Filename</code> , <code>ProcessorID</code> .
<code>nifi.provenance.repository.indexed.attributes</code>	This is a comma-separated list of FlowFile Attributes that should be indexed and made searchable. It is blank by default. But some good examples to consider are 'filename' and 'mime.type' as well as any custom attributes you might use which are valuable for your use case.
<code>nifi.provenance.repository.index.shard.size</code>	The repository uses Apache Lucene to performing indexing and searching capabilities. This value indicates how large a Lucene Index should become before the Repository starts writing to a new Index. Large values for the shard size will result in more Java heap usage when searching the Provenance Repository but should provide better performance. The default value is 500 MB. However, this is due to the fact that defaults are tuned for very small environments where most users begin to use NiFi. For

	production environments, it is advisable to change this value to 4 to 8 GB . Once all Provenance Events in the index have been aged off from the "event files," the index will be destroyed as well.
nifi.provenance.repository.max.attribute.length	Indicates the maximum length that a FlowFile attribute can be when retrieving a Provenance Event from the repository. If the length of any attribute exceeds this value, it will be truncated when the event is retrieved. The default value is 65536.
nifi.provenance.repository.concurrent.merge.threads	Apache Lucene creates several "segments" in an Index. These segments are periodically merged together in order to provide faster querying. This property specifies the maximum number of threads that are allowed to be used for each of the storage directories. The default value is 2. For high throughput environments, it is advisable to set the number of index threads larger than the number of merge threads * the number of storage locations. For example, if there are 2 storage locations and the number of index threads is set to 8, then the number of merge threads should likely be less than 4. While it is not critical that this be done, setting the number of merge threads larger than this can result in all index threads being used to merge, which would cause the NiFi flow to periodically pause while indexing is happening, resulting in some data being processed with much higher latency than other data.
nifi.provenance.repository.warm.cache.frequency	Each time that a Provenance query is run, the query must first search the Apache Lucene indices (at least, in most cases - there are some queries that are run often and the results are cached to avoid searching the Lucene indices). When a Lucene index is opened for the first time, it can be very expensive and take several seconds. This is compounded by having many different indices, and can result in a Provenance query taking much longer. After the index has been opened, the Operating System's disk cache will typically hold onto enough data to make re-opening the index much faster - at least for a period of time, until the disk cache evicts this data. If this value is set, NiFi will periodically open each Lucene index and then close it, in order to "warm" the cache. This will result in far faster queries when the Provenance Repository is large. As with all great things, though, it comes with a cost. Warming the cache does take some CPU resources, but more importantly it will evict other data from the Operating System disk cache and will result in reading (potentially a great deal of) data from the disk. This can result in lower NiFi performance. However, if NiFi is running in an environment where CPU and disk are not fully utilized, this feature can result in far faster Provenance queries. The default value for this property is blank (i.e. disabled).

1.1.14.13. Encrypted Write Ahead Provenance Repository Properties

All of the properties defined above (see [Write Ahead Repository Properties](#)) still apply. Only encryption-specific properties are listed here. See [Encrypted Provenance Repository](#) in the User Guide for more information.

Property	Description
nifi.provenance.repository.debug.frequency	Controls the number of events processed between DEBUG statements documenting the performance metrics of the repository. This value is only used when DEBUG level statements are enabled in the log configuration.

nifi.provenance.repository.encryption.key.provider.implementation	This is the fully-qualified class name of the key provider . A key provider is the datastore interface for accessing the encryption key to protect the provenance events. There are currently two implementations - <code>StaticKeyProvider</code> which reads a key directly from <code>nifi.properties</code> , and <code>FileBasedKeyProvider</code> which reads <code>n</code> many keys from an encrypted file. The interface is extensible, and HSM-backed or other providers are expected in the future.
nifi.provenance.repository.encryption.key.provider.location	The path to the key definition resource (empty for <code>StaticKeyProvider</code> , <code>./keys.nkp</code> or similar path for <code>FileBasedKeyProvider</code>). For future providers like an HSM, this may be a connection string or URL.
nifi.provenance.repository.encryption.key.id	The active key ID to use for encryption (e.g. <code>Key1</code>).
nifi.provenance.repository.encryption.key	The key to use for <code>StaticKeyProvider</code> . The key format is hex-encoded (0123456789ABCDEFEDCBA98765432100123456789ABCDEFEDCBA98765432100123456789ABCDEFEDCBA9876543210) but can also be encrypted using the <code>./encrypt-config.sh</code> tool in NiFi Toolkit.
nifi.provenance.repository.encryption.key.id.*	Allows for additional keys to be specified for the <code>StaticKeyProvider</code> . For example, the line <code>nifi.provenance.repository.encryption.key.id.Key2=012...210</code> would provide an available key <code>Key2</code> .

The simplest configuration is below:

```
nifi.provenance.repository.implementation=org.apache.nifi.provenance.
EncryptedWriteAheadProvenanceRepository
nifi.provenance.repository.debug.frequency=100
nifi.provenance.repository.encryption.key.provider.implementation=org.apache.
nifi.security.kms.StaticKeyProvider
nifi.provenance.repository.encryption.key.provider.location=
nifi.provenance.repository.encryption.key.id=Key1
nifi.provenance.repository.encryption.key=
0123456789ABCDEFEDCBA98765432100123456789ABCDEFEDCBA9876543210
```

1.1.14.14. Component Status Repository

The Component Status Repository contains the information for the Component Status History tool in the User Interface. These properties govern how that tool works.

The `buffer.size` and `snapshot.frequency` work together to determine the amount of historical data to retain. As an example to configure two days worth of historical data with a data point snapshot occurring every 5 minutes you would configure `snapshot.frequency` to be "5 mins" and the `buffer.size` to be "576". To further explain this example for every 60 minutes there are 12 (60 / 5) snapshot windows for that time period. To keep that data for 48 hours (12 * 48) you end up with a buffer size of 576.

Property	Description
nifi.components.status.repository.implementation	The Component Status Repository implementation. The default value is <code>org.apache.nifi.controller.status.history.VolatileComponentStatusRepository</code> and should not be changed.
nifi.components.status.repository.buffer.size	Specifies the buffer size for the Component Status Repository. The default value is 1440.
nifi.components.status.snapshot.frequency	This value indicates how often to present a snapshot of the components' status history. The default value is 1 min.

1.1.14.15. Site to Site Properties

These properties govern how this instance of NiFi communicates with remote instances of NiFi when Remote Process Groups are configured in the dataflow. Remote Process Groups can choose transport protocol from RAW and HTTP. Properties named with *nifi.remote.input.socket.** are RAW transport protocol specific. Similarly, *nifi.remote.input.http.** are HTTP transport protocol specific properties.

Property	Description
nifi.remote.input.host	The host name that will be given out to clients to connect to this NiFi instance for Site-to-Site communication. By default, it is the value from <code>InetAddress.getLocalHost().getHostName()</code> . On UNIX-like operating systems, this is typically the output from the <code>hostname</code> command.
nifi.remote.input.secure	This indicates whether communication between this instance of NiFi and remote NiFi instances should be secure. By default, it is set to <code>false</code> . In order for secure site-to-site to work, set the property to <code>true</code> . Many other Security Properties (below) must also be configured.
nifi.remote.input.socket.port	The remote input socket port for Site-to-Site communication. By default, it is blank, but it must have a value in order to use RAW socket as transport protocol for Site-to-Site.
nifi.remote.input.http.enabled	Specifies whether HTTP Site-to-Site should be enabled on this host. By default, it is set to <code>true</code> . Whether a Site-to-Site client uses HTTP or HTTPS is determined by <code>nifi.remote.input.secure</code> . If it is set to <code>true</code> , then requests are sent as HTTPS to <code>nifi.web.https.port</code> . If set to <code>false</code> , HTTP requests are sent to <code>nifi.web.http.port</code> .
nifi.remote.input.http.transaction.ttl	Specifies how long a transaction can stay alive on the server. By default, it is set to <code>30 secs</code> . If a Site-to-Site client hasn't proceeded to the next action after this period of time, the transaction is discarded from the remote NiFi instance. For example, when a client creates a transaction but doesn't send or receive flow files, or when a client sends or receives flow files but doesn't confirm that transaction.
nifi.remote.contents.cache.expiration	Specifies how long NiFi should cache information about a remote NiFi instance when communicating via Site-to-Site. By default, NiFi will cache the responses from the remote system for <code>30 secs</code> . This allows NiFi to avoid constantly making HTTP requests to the remote system, which is particularly important when this instance of NiFi has many instances of Remote Process Groups.

1.1.14.16. Web Properties

These properties pertain to the web-based User Interface.

Property	Description
nifi.web.war.directory	This is the location of the web war directory. The default value is <code>./lib</code> .
nifi.web.http.host	The HTTP host. It is blank by default.

<code>nifi.web.http.port</code>	The HTTP port. The default value is 8080.
<code>nifi.web.http.port.forwarding</code>	The port which forwards incoming HTTP requests to <code>nifi.web.http.host</code> . This property is designed to be used with 'port forwarding', when NiFi has to be started by a non-root user for better security, yet it needs to be accessed via low port to go through a firewall. For example, to expose NiFi via HTTP protocol on port 80, but actually listening on port 8080, you need to configure OS level port forwarding such as <code>iptables</code> (Linux/Unix) or <code>pfctl</code> (OS X) that redirects requests from 80 to 8080. Then set <code>nifi.web.http.port</code> as 8080, and <code>nifi.web.http.port.forwarding</code> as 80. It is blank by default.
<code>nifi.web.http.network.interface*</code>	<p>The name of the network interface to which NiFi should bind for HTTP requests. It is blank by default.</p> <p>NOTE: Multiple network interfaces can be specified by using the <code>nifi.web.http.network.interface</code>. prefix with unique suffixes and separate network interface names as values.</p> <p>For example, to provide two additional network interfaces, a user could also specify additional properties with keys of:</p> <pre>nifi.web.http.network.interface.eth0=eth0 nifi.web.http.network.interface.eth1=eth1</pre> <p>Providing three total network interfaces, including <code>nifi.web.http.network.interface.default</code>.</p>
<code>nifi.web.https.host</code>	The HTTPS host. It is blank by default.
<code>nifi.web.https.port</code>	The HTTPS port. It is blank by default. When configuring NiFi to run securely, this port should be configured.
<code>nifi.web.https.port.forwarding</code>	Same as <code>nifi.web.http.port.forwarding</code> , but with HTTPS for secure communication. It is blank by default.
<code>nifi.web.https.network.interface*</code>	<p>The name of the network interface to which NiFi should bind for HTTPS requests. It is blank by default.</p> <p>NOTE: Multiple network interfaces can be specified by using the <code>nifi.web.https.network.interface</code>. prefix with unique suffixes and separate network interface names as values.</p> <p>For example, to provide two additional network interfaces, a user could also specify additional properties with keys of:</p> <pre>nifi.web.https.network.interface.eth0=eth0 nifi.web.https.network.interface.eth1=eth1</pre> <p>Providing three total network interfaces, including <code>nifi.web.https.network.interface.default</code>.</p>
<code>nifi.web.jetty.working.directory</code>	The location of the Jetty working directory. The default value is <code>./work/jetty</code> .
<code>nifi.web.jetty.threads</code>	The number of Jetty threads. The default value is 200.
<code>nifi.web.max.header.size</code>	The maximum size allowed for request and response headers. The default value is 16 KB.

1.1.14.17. Security Properties

These properties pertain to various security features in NiFi. Many of these properties are covered in more detail in the Security Configuration section of this Administrator's Guide.

Property	Description
nifi.sensitive.props.key	This is the password used to encrypt any sensitive property values that are configured in processors. By default, it is blank, but the system administrator should provide a value for it. It can be a string of any length, although the recommended minimum length is 10 characters. Be aware that once this password is set and one or more sensitive processor properties have been configured, this password should not be changed.
nifi.sensitive.props.algorithm	The algorithm used to encrypt sensitive properties. The default value is PBEWITHMD5AND256BITAES-CBC-OPENSSL.
nifi.sensitive.props.provider	The sensitive property provider. The default value is BC.
nifi.sensitive.props.additional.keys	The comma separated list of properties to encrypt in addition to the default sensitive properties (see Encrypt-Config Tool).
nifi.security.keystore*	The full path and name of the keystore. It is blank by default.
nifi.security.keystoreType	The keystore type. It is blank by default.
nifi.security.keystorePasswd	The keystore password. It is blank by default.
nifi.security.keyPasswd	The key password. It is blank by default.
nifi.security.truststore*	The full path and name of the truststore. It is blank by default.
nifi.security.truststoreType	The truststore type. It is blank by default.
nifi.security.truststorePasswd	The truststore password. It is blank by default.
nifi.security.needClientAuth	This indicates whether client authentication in the cluster protocol. It is blank by default.
nifi.security.user.authorizer	Specifies which of the configured Authorizers in the authorizers.xml file to use. By default, it is set to file-provider.
nifi.security.user.login.identity.provider	This indicates what type of login identity provider to use. The default value is blank, can be set to the identifier from a provider in the file specified in <code>nifi.login.identity.provider.configuration.file</code> . Setting this property will trigger NiFi to support username/password authentication.
nifi.security.ocsp.responder.url	This is the URL for the Online Certificate Status Protocol (OCSP) responder if one is being used. It is blank by default.
nifi.security.ocsp.responder.certificate	This is the location of the OCSP responder certificate if one is being used. It is blank by default.

1.1.14.18. Identity Mapping Properties

These properties can be utilized to normalize user identities. When implemented, identities authenticated by different identity providers (certificates, LDAP, Kerberos) are treated the same internally in NiFi. As a result, duplicate users are avoided and user-specific configurations such as authorizations only need to be setup once per user.

The following examples demonstrate normalizing DN's from certificates and principals from Kerberos:

```
nifi.security.identity.mapping.pattern.dn=^CN=(.*?), OU=(.*?), O=(.*?), L=(.*?)
), ST=(.*?), C=(.*?)$
nifi.security.identity.mapping.value.dn=$1@$2
nifi.security.identity.mapping.pattern.kerb=^(.*?)/instance@(.*?)$
nifi.security.identity.mapping.value.kerb=$1@$2
```

The last segment of each property is an identifier used to associate the pattern with the replacement value. When a user makes a request to NiFi, their identity is checked to see if it matches each of those patterns in lexicographical order. For the first one that matches, the replacement specified in the `nifi.security.identity.mapping.value.xxxx` property is used. So a login with `CN=localhost, OU=Apache NiFi, O=Apache, L=Santa Monica, ST=CA, C=US` matches the DN mapping pattern above and the DN mapping value `$1@$2` is applied. The user is normalized to `localhost@Apache NiFi`.

These mappings are also applied to the "Initial Admin Identity" and "Cluster Node Identity" properties in the `authorizers.xml` file (See [Authorizers.xml Setup](#)).

1.1.14.19. Cluster Common Properties

When setting up a NiFi cluster, these properties should be configured the same way on all nodes.

Property	Description
<code>nifi.cluster.protocol.heartbeat.interval</code>	The interval at which nodes should emit heartbeats to the Cluster Coordinator. The default value is 5 <code>sec</code> .
<code>nifi.cluster.protocol.is.secure</code>	This indicates whether cluster communications are secure. The default value is <code>false</code> .

1.1.14.20. Cluster Node Properties

Configure these properties for cluster nodes.

Property	Description
<code>nifi.cluster.is.node</code>	Set this to <code>true</code> if the instance is a node in a cluster. The default value is <code>false</code> .
<code>nifi.cluster.node.address</code>	The fully qualified address of the node. It is blank by default.
<code>nifi.cluster.node.protocol.port</code>	The node's protocol port. It is blank by default.
<code>nifi.cluster.node.protocol.threads</code>	The number of threads that should be used to communicate with other nodes in the cluster. This property defaults to 10, but for large clusters, this value may need to be larger.
<code>nifi.cluster.node.protocol.max.threads</code>	The maximum number of threads that should be used to communicate with other nodes in the cluster. This property defaults to 50.
<code>nifi.cluster.node.event.history.size</code>	When the state of a node in the cluster is changed, an event is generated and can be viewed in the Cluster page. This value indicates how many events to keep in memory for each node. The default value is 25.
<code>nifi.cluster.node.connection.timeout</code>	When connecting to another node in the cluster, specifies how long this node should wait before considering the connection a failure. The default value is 5 <code>secs</code> .
<code>nifi.cluster.node.read.timeout</code>	When communicating with another node in the cluster, specifies how long this node should wait to receive information from the remote node before considering the

	communication with the node a failure. The default value is 5 secs.
nifi.cluster.firewall.file	The location of the node firewall file. This is a file that may be used to list all the nodes that are allowed to connect to the cluster. It provides an additional layer of security. This value is blank by default, meaning that no firewall file is to be used.
nifi.cluster.flow.election.max.wait.time	Specifies the amount of time to wait before electing a Flow as the "correct" Flow. If the number of Nodes that have voted is equal to the number specified by the <code>nifi.cluster.flow.election.max.candidates</code> property, the cluster will not wait this long. The default value is 5 mins. Note that the time starts as soon as the first vote is cast.
nifi.cluster.flow.election.max.candidates	Specifies the number of Nodes required in the cluster to cause early election of Flows. This allows the Nodes in the cluster to avoid having to wait a long time before starting processing if we reach at least this number of nodes in the cluster.

1.1.14.21. Claim Management

Whenever a request is made to change the dataflow, it is important that all nodes in the NiFi cluster are kept in-sync. In order to allow for this, NiFi employs a two-phase commit. The request is first replicated to all nodes in the cluster, simply asking whether or not the request is allowed. Each node then determines whether or not it will allow the request and if so issues a "Claim" on the component(s) being modified. This claim can be thought of as a mutually-exclusive lock that is owned by the requestor. Once all nodes have voted on whether or not the request is allowed, the node from which the request originated must decide whether or not to complete the request. If any node voted 'NO' then the request is canceled and the Claim is canceled with an error message sent back to the user. However, if the nodes all vote 'YES' then the request is completed. In this sort of distributed environment, it is possible that the node that made the original request will fail after the voting has occurred and before the request was completed. This would leave the component locked indefinitely so that no more changes can be made to the component. In order to avoid this, the Claim will time out after some period of time. These properties determines how these locks are managed.

Property	Description
nifi.cluster.request.replication.claim.timeout	Specifies how long to wait before considering a lock 'expired' and automatically unlocking.

1.1.14.22. ZooKeeper Properties

NiFi depends on Apache ZooKeeper for determining which node in the cluster should play the role of Primary Node and which node should play the role of Cluster Coordinator. These properties must be configured in order for NiFi to join a cluster.

Property	Description
nifi.zookeeper.connect.string	The Connect String that is needed to connect to Apache ZooKeeper. This is a comma-separated list of hostname:port pairs. For example, <code>localhost:2181,localhost:2182,localhost:2183</code> . This should contain a list of all ZooKeeper instances in the ZooKeeper quorum. This property must be specified to join a cluster and has no default value.

nifi.zookeeper.connect.timeout	How long to wait when connecting to ZooKeeper before considering the connection a failure. The default value is 3 secs.
nifi.zookeeper.session.timeout	How long to wait after losing a connection to ZooKeeper before the session is expired. The default value is 3 secs.
nifi.zookeeper.root.node	The root ZNode that should be used in ZooKeeper. ZooKeeper provides a directory-like structure for storing data. Each 'directory' in this structure is referred to as a ZNode. This denotes the root ZNode, or 'directory', that should be used for storing data. The default value is /root. This is important to set correctly, as which cluster the NiFi instance attempts to join is determined by which ZooKeeper instance it connects to and the ZooKeeper Root Node that is specified.

1.1.14.23. Kerberos Properties

Property	Description
nifi.kerberos.krb5.file*	The location of the krb5 file, if used. It is blank by default. At this time, only a single krb5 file is allowed to be specified per NiFi instance, so this property is configured here to support SPNEGO and service principals rather than in individual Processors. If necessary the krb5 file can support multiple realms. Example: /etc/krb5.conf
nifi.kerberos.service.principal*	The name of the NiFi Kerberos service principal, if used. It is blank by default. Note that this property is for NiFi to authenticate as a client other systems. Example: nifi/nifi.example.com or nifi/nifi.example.com@EXAMPLE.COM
nifi.kerberos.service.keytab.location*	The file path of the NiFi Kerberos keytab, if used. It is blank by default. Note that this property is for NiFi to authenticate as a client other systems. Example: /etc/nifi.keytab
nifi.kerberos.spnego.principal*	The name of the NiFi Kerberos service principal, if used. It is blank by default. Note that this property is used to authenticate NiFi users. Example: HTTP/nifi.example.com or HTTP/nifi.example.com@EXAMPLE.COM
nifi.kerberos.spnego.keytab.location*	The file path of the NiFi Kerberos keytab, if used. It is blank by default. Note that this property is used to authenticate NiFi users. Example: /etc/http-nifi.keytab
nifi.kerberos.spnego.authentication.expiration*	The expiration duration of a successful Kerberos user authentication, if used. The default value is 12 hours.

1.1.14.24. Custom Properties

To configure custom properties for use with NiFi's Expression Language:

- Create the custom property. Ensure that:
 - Each custom property contains a distinct property value, so that it is not overridden by existing environment properties, system properties, or FlowFile attributes.
 - Each node in a clustered environment is configured with the same custom properties.
- Update `nifi.variable.registry.properties` with the location of the custom property file(s):

Property	Description
nifi.variable.registry.properties	This is a comma-separated list of file location paths for one or more custom property files.

- Restart your NiFi instance(s) for the updates to be picked up.

Custom properties can also be configured in the NiFi UI. See the [Variables Window](#) section in the User Guide for more information.

Upgrading Take care when configuring the properties above that are marked with an asterisk (*). To make the upgrade process easier, it is advisable to change the default configurations to locations outside the main root installation directory. In this way, these items can remain in their configured location through an upgrade, and NiFi can find all the repositories and configuration files and pick up where it left off as soon as the old version is stopped and the new version is started. Furthermore, the administrator may reuse this *nifi.properties* file and any other configuration files without having to re-configure them each time an upgrade takes place. As previously noted, it is important to check for any changes in the *nifi.properties* file of the new version when upgrading and make sure they are reflected in the *nifi.properties* file you use.